MS112 - calibrate and atmospherically correct ocean color data

## **SYNOPSIS**

MSl12 par=file

– or –

MSl12 ifile=ifile ofile1=ofile1

– or –

MSl12 ifile=ifile ofile1=ofile1 [ def\_12prod\_file=def\_12prod\_file ] [ 12prod1=12prod1 ] [ ofile[#]=ofile[#] ] [ 12prod[#]=12prod[#] ] [ spixl=spixl ] [ epixl=epixl ] [ dpixl=dpixl ] [ sline=sline ] [ eline=eline ] [ dline=dline ] [ ctl\_pt\_incr=ctl\_pt\_incr ] [ aer\_opt=aer\_opt ] [ aer\_iter\_min=aer\_iter\_min ] [ aer\_iter\_max=aer\_iter\_max ] [ tau\_a=tau\_a ] [ glint\_opt=glint\_opt ] [ outband\_opt=outband\_opt ] [ oxaband\_opt=oxaband\_opt ] [ carder\_opt=carder\_opt ] [ filter\_opt=filter\_opt ] [ filter\_file=filter\_file ] [ calfile=calfile ] [ vcal\_opt=vcal\_opt ] [ offset=offset ] [ gain=gain ] [ albedo=albedo ] [ glint\_thresh=glint\_thresh] [ absaer=absaer ] [ sunzen=sunzen ] [ satzen=satzen ] [ epsmin=epsmin ] [ epsmax=epsmax ] [ tauamax=tauamax ] [ nlwmin=nlwmin ] [ wsmax=wsmax ] [ maskland=maskland ] [ maskbath=maskbath ] [ maskcloud=maskcloud ] [ maskglint=maskglint ] [ masksunzen=masksunzen ] [ sl\_pixl=sl\_pixl ] [ met1=met1 ] [ met2=met2 ] [ met3=met3 ] [ ozone1=ozone1 ] [ ozone2=ozone2 ] [ ozone3=ozone3 ] [ land=land ] [ water=water ] [ elev=elev ]

## **DESCRIPTION**

This program is capable of performing atmospheric correction of top-of-atmosphere (TOA) radiances from several ocean remote sensing, spaceborne spectrometers, including SeaWiFS and MOS, and deriving atmospheric and bio-optical properities using identical algorithms for both sensors. Data input format and sensor identification are automatically determined by the program, which presently recognizes SeaWiFS Level–1A or Level–1B, and MOS Level–1B. Sensor dependent details such as band-pass-weighted quantities are included in a sensor-specific external data file, and pre-computed sensor-specific look-up tables are provided for Rayleigh scattering and Rayleigh-aerosol transmittance. Aerosol model tables make use of SeaWiFS-specific coefficients, with some adjustment of the model epsilons to correct for deviations from SeaWiFS center wavelengths. The use of pre-computed SeaWiFS aerosol tables limits the ability of MS112 to perform atmospheric correction to sensors that do not signficantly deviate from SeaWiFS wavelengths, or sensors that contain no more than six wavelengths in the 400–700 nm.

# **PRODUCTS**

This table contains all the products (don't get dizzy) which are available from this one program! Most outputs are 2-D arrays stored in an HDF file as a Scientific Data Sets (SDS) with the given name. The products which contain *nnn* are available at each wavelength of the given sensor. For SeaWiFs these are: 412, 443, 490, 510, 555, 670, 765, and 865; for MOS these are: 408, 443, 485, 520, 570, 685, 750, and 870; and for OCTS these are: 412, 443, 490, 520, 565, 670, 765, and 865. For the eps\_*nnn\_lll* product, *lll* represents the longest wavength, that is, 865 for SeaWiFS and OCTS or 870 for MOS. Note that some products have multiple names for the same exact product. This is due to the nature of HDF's SDS interface wherein each SDS must have a unique name. Duplicate names are used for compatability between several systems which use the same code (SeaDAS, SeaWiFS Project, and NRL).

Product Description

rrs\_nnn remote sensing reflectance at nnn nm

nLw\_nnn normalized water-leaving radiance at nnn nm

Lw\_nnnwater-leaving radiance at nnn nmLr\_nnnRayleigh radiance at nnn nmLa\_nnnaerosol radiance at nnn nmTLg\_nnnTOA glint radiance at nnn nmtLf\_nnnfoam (white-cap) radiance at nnn nmLt\_nnncalibrated TOA radiance at nnn nm

t\_sol\_nnn Rayleigh-aerosol transmittance,sun to ground at nnn nm t\_sen\_nnn Rayleigh-aerosol transmittance,ground to sensor at nnn nm

t\_oz\_sol\_*nnn* ozone transmittance,sun to ground at *nnn* nm t\_oz\_sen\_*nnn* ozone transmittance,ground to sensor at *nnn* nm

taua\_nnn aerosol optical depth at nnn nm

tau\_nnn same as taua\_nnn

angstrom\_nnn aerosol angstrom coefficents (nnn,865) nm

eps\_nnn\_lll ratio of nnn to lll single-scattering aerosol radiances

Es\_nnn extra-terestrial surface irradiance at nnn nm

rhos\_nnn surface reflectance at nnn nm t\_o2\_nnn total oxygen transmittance at nnn nm foq\_nnn f/Q correction to nadir at nnn nm

a\_nnn\_arnone total absorption at nnn nm using Arnone algorithm
bb\_nnn\_arnone backscatter at nnn nm using Arnone algorithm
b\_nnn\_arnone total scattering at nnn nm using Arnone algorithm
c\_nnn\_arnone beam attenuation at nnn nm using Arnone algorithm
a\_nnn\_carder total absorption at nnn nm using Carder algorithm

aph\_nnn\_carder phytoplankton absorption at nnn nm using Carder algorithm adg\_nnn\_carder detris/gelbstuff absorption at nnn nm using Carder algorithm

bb nnn carder backscatter at nnn nm using Carder algorithm b *nnn* carder total scattering at *nnn* nm using Carder algorithm c\_nnn\_carder beam attenuation at nnn nm using Carder algorithm agmod\_carder Modeled value for ag(400) from Carder's algorithm Default value for ag(400) from Carder's algorithm agdef\_carder aphmod\_carder Modeled value for aph(675) from Carder's algorithm aphdef carder Default value for aph(675) from Carder's algorithm beam attenuation length at nnn nm using Carder algorithm c length *nnn* carder

a\_nnn\_qaa total absorption at nnn nm using QAA algorithm

aph\_nnn\_qaa phytoplankton absorption at nnn nm using QAA algorithm adg\_nnn\_qaa detris/gelbstuff absorption at nnn nm using QAA algorithm

bb\_nnn\_qaa backscatter at nnn nm using QAA algorithm
b\_nnn\_qaa total scattering at nnn nm using QAA algorithm
c\_nnn\_qaa beam attenuation at nnn nm using QAA algorithm

aph\_443\_stumpf phytoplankton absorption at 443 nm using Stumpf's algorithm DOM and gelbstuff absorption at 412 nm using Stumpf's algorithm DOM and gelbstuff absorption at 555 nm using Stumpf's algorithm

a\_412\_stumpf total absorption at 412 nm using Stumpf's algorithm a\_555\_stumpf total absorption at 555 nm using Stumpf's algorithm chl\_oc2 chlorophyll-a concentration using OC2 algorithm chl\_oc4 chlorophyll-a concentration using OC4 algorithm

chlor\_a same as chl\_oc4

chl\_stumpf chlorophyll-a concentration using Stumpf's algorithm chl\_carder chlorophyll-a concentration using Carder's algorithm chl\_octsc chlorophyll-a concentration using the OCTS-C algorithm chl\_nn chlorophyll-a concentration derived from pig\_nn data chl\_ndpi chlorophyll-a concentration derived from pig\_ndpi data

chl\_trees chlorophyll-a using Tree's algorithm

pig\_oc2 pigment concentration derived from chl\_oc2

CZCS\_pigment same as pig\_oc2 pigment\_czcs same as pig\_oc2 pigment\_seabam same as pig\_oc2

pig oc4 pigment concentration derived from chl oc4

pigment same as pig\_oc4

pig\_octsc pigment concentration derived from chl\_octsc

pig\_nn pigment concentration using neural network algorithm

pig\_ndpi pigment concentration using normalized diffence pigment index

K\_490 diffuse attenuation at 490 nm using 443/555 ratio

k490 same as K 490

K\_length\_532 diffuse attenuation at 532 nm using 443/555 ratio K\_532 diffuse attenuation at 532 nm using 490/555 ratio

K\_532\_Mueller same as K\_532 k532 same as K\_532

ndvi normalized difference vegetation index

evi enhanced vegetation index

depth water depth index

par photosynthetically active radiation

aerindex aerosol index

aer\_model\_min minimum bounding aerosol model #
aer\_model\_max maximum bounding aerosol model #

aer\_model\_ratio model mixing ratio

aer\_num\_iter number of aerosol iterations, NIR correction glint\_coeff glint radiance normalized by solar irradiance

12\_flags level-2 processing flags

epsilon retreived epsilon used for model selection

eps\_78 same as epsilon cloud\_albedo cloud albedo at 865 nm lats latitudes (-90.0 to 90.0) longs longitudes (-180.0 to 180.0)

solzsolar zenith anglesolasolar azimuth anglesenzsatellite zenith anglesenasatellite azimuth angle

windspeed magnitude of wind at 10 meters
zwind zonal wind speed at 10 meters
mwind meridional wind speed at 10 meters

windangle wind direction at 10 meters water vapor precipital water concentration

humidity relative humidity pressure barometric pressure ozone ozone concentration

fsol solar distance correction (1-D, not an image)

smoke smoke index

N\_small\_particles number of small particles using Haltrin's algorithm
N\_large\_particles number of small particles using Haltrin's algorithm
N\_particles number of small particles using Haltrin's algorithm

salinity salinity using Arnone's algorithm visibility\_nnn diver visibility using 6.1/c (McBride) horiz\_vis horizontal diver visibility using 4.8/c vert\_vis vertical diver visibility using 4.0/(c+Kd)

### **OPTIONS**

Each of these options listed below must be placed on the command line or in the parameter files as keyword=value pairs. If the environment variables (see "ENVIRONMENTAL VARIABLES" below) are defined, then the only required keyword=value pairs are ifile and ofile1. The others have reasonable defaults.

par Input parameter file to be used in the specific command mode msl12, par="pfile". The parameter file is a text file containing the user-defined keyword=value pairs, each on a single line.

## **Input/Output File**

MSl12 has the ability to output up to four seperate files each with their own list of products (ofile1, ofile2, ofile3, and ofile4 contain the names of each file, and l2prod1, l2prod2, l2prod3, and l2prod4 contain the list of desired products for each output file). This allows the user to seperate products into various output files.

- ifile Directory path and filename of the input level-1A data product. An OCTS input must be either a NASDA L1B format file or a SIMBIOS-format L1B file (generated by 11bocts). A MOS input must be MOS-B L1B data. A SeaWiFs input may be either a L1A or L1B file.
- ofile1 Directory path and filename of the output Level–2 HDF file containing the products specified in the defaults file def\_l2prod\_file or by the **l2prod1** keyword.

## def\_l2prod\_file

The file containing the default output products by files. (Default=\$MSL12\_DATA/sensor/sensor\_def\_12prod.dat.)

### 12prod1

The product names (see main description section above) to be output to ofile1.

## ofile[2-4]

Directory path and filename of the output L2 files containing the products specified in the default file def 12prod file or by the 12prod[2-4] keyword.

## 12prod[2-4]

The product names (see main description section above) to be output to ofile[2-4].

ofmt *n* This keyword defines the type of file output. If set to 0 or 1, a flat binary type of format is written. The default value of 2, creates the standard NASA HDF fileformat. A value of 3 will produce an NRL HDF fileformat.

### **Input File Parameters**

**MSl12** has the ability to subsection/subsample the input file and to control the number of control points in each output file. If not specified, MSl12 will work on the entire input file.

- spixl Starting pixel to be processed (default=1)
- epixl End pixel to be processed (default=0, meaning the last pixel in the scan line)
- dpixl Pixel subsampling interval (default=1)

sline Starting line number to be processed (default=1)

eline Ending line number to be processed (default=0, meaning the last line in file)

dline Line subsampling interval (default=1)

ctl pt incr

Control-point pixel increment for lon/lat arrays (0=optimize, default=8)

## **Calibration Control Options**

These keywords control the calibration of the input data.

calfile Directory path and filename of the input calibration table file. The default is \$CAL\_HDF\_PATH.

vcal\_opt

Control for calibration modification: 0 - use gain, offset from the calibration table 1 - use the gain (as multipliers of the existing gains in the table file) from the input (gain) and offset from the calibration table 2 - use offsets from the input (offset) and the gains from the calibration table 3 - use both gain (as multipliers of the existing gains in the table file) and offset from the input (gain & offset)

gain Calibration gain factors to multiply the gain values read from the \$MSL12\_DATA/sensor/sensor\_table.dat file. Defaults to [0.0,0.0,0.0,0.0,0.0,0.0,0.0].

offset Calibration gain offset factors to substitute for values read from the calibration table. Defaults to [1.0,1.0,1.0,1.0,1.0,1.0,1.0,1.0].

### **Ancillary Input Files**

These keywords control the ancilliary input files. If the environment variables have been set (see "ENVI-RONMENTAL VARIABLES"), then these keywords have reasonable defaults. If they are not set, then the user *must* define these: land, water, met1, and ozone1.

land Directory path and filename of the land-mask input file. Default is \$MSL12\_DATA/landmask.dat

water Directory path and filename of the shallow water mask input file used for setting the l2\_flags bit to indicate shallow water (defined as 30m) areas (McClain et al., 1995). Default is \$MSL12\_DATA/watermask.dat

met1 Directory path and filename of the climatological product or the near-real-time (NRT) meteorological ancillary data product available for the nearest time preceding the time of ifile product's first scan line. If met1 is the climatological file, then met2 and met3 will not be used, otherwise, see met2 for logic. Default is \$MSL1\_DATA/CLIMATOLOGY.MET.

met2 Directory path and filename of the NRT meteorological ancillary data product available for the nearest time following the time of ifile product's first scan line's. If met2 is not specified (null) and met1 is a NRT product, then met2 will be set to met1. If met1 <> met2 and the scan line's date and time, fall between the times of met1 and met2, get\_ancillary will use met1 and met2 to generate the interpolated meteorological values (if the scan line's date and time fall before those of met1, an error occurs). If met1 = met2 and the scan line's date and time fall before met2,

get\_ancillary will use only met2 to generate the meteorological values. If met2 <> met3 and the scan line's date and time fall between the times of met2 and met3, get\_ancillary will use met2 and met3 to generate the interpolated meteorological values (if the scan line's date and time fall after those of met3, an error occurs). If met2 = met3 and the scan line's date and time fall after met2, get ancillary will use only met2 to generate the meteorological values.

met3 Directory path and filename of the NRT meteorological ancillary data product for the nearest time following the time of ifile product's last scan line. If met3 is not specified (null) and met1 is a NRT product, then met3 will be set to met2 and the logic specified in met2 will be applied.

ozone1 Directory path and filename of the climatological product or the NRT ozone ancillary data product available for the nearest time preceding the time of ifile product's first scan line. If ozone1 is the climatological file, then ozone2 and ozone3 will not be used, otherwise see ozone2 for logic. (For TOVS data, the center point time is used to represent the time of that product.) Defaults to \$MSL12 DATA/CLIMATOLOTY.OZONE.

ozone2 Directory path and filename of the NRT ozone ancillary data product available for the nearest time following the time of ifile product's first scan line's. If ozone2 is not specified (null) and ozone1 is a NRT product, then ozone2 will be set to ozone1. If ozone1 <> ozone2 and the scan line's date and time, fall between the times of ozone1 and ozone2, get\_ancillary will use ozone1 and ozone2 to generate the interpolated ozone values (if the scan line's date and time fall before those of ozone1, an error occurs). If ozone1 = ozone2 and the scan line's date and time fall before ozone2, get\_ancillary will use only ozone2 to generate the ozone values. If ozone2 <> ozone3 and the scan line's date and time fall between the times of ozone2 and ozone3, get\_ancillary will use ozone2 and ozone3 to generate the interpolated ozone values (if the scan line's date and time fall after those of ozone3, an error occurs). If ozone2 = ozone3 and the scan line's date and time fall after ozone2, get\_ancillary will use only ozone2 to generate the ozone values. (For TOVS data, the center point time is used to represent the time of that product.)

ozone3 Directory path and filename of the NRT ozone ancillary data product for the nearest time following the time of ifile product's last scan line. If ozone3 is not specified (null) and ozone1 is a NRT product, then ozone3 will be set to ozone2 and the logic specified in ozone2 will be applied. (For TOVS data, the center point time is used to represent the time of that product.)

## **Algorithm control options**

These keywords modify and/or select the algorithms used to correct the input data or change certain thresholds used for various tests.

### carder\_opt

This option selects the parameters to use for Carder's algorithm. 0=global parameters (default), 1=unpackaged parameters, 2=packaged parameters 3=hyper-packaged parameters, 4=use an remote sensing reflectance filter to select either global, unpackaged, or packaged parameters, 5=use the value read from the parameter file.

## carder\_version

This option selects the version of the Carder algorithm to use. 0=version 1.3, 1=version 1.33, 2=version 1.4 Version 1.33 adds the estimates for default aph\_mod and ag\_mod and blends these with the modeled values. Version 1.4 add the hyperpacked parameters.

## carder\_iter

This option turns on the s iteration in Carder's algorithm. 0=off, 1=on.

## carder\_gain

Calibration gain factors to multiply the remote sensing reflectance values passed into the carder function. Defaults to [1.0,1.0,1.0,1.0,1.0,1.0].

## filter\_opt

Option for filtering the L1B data with the method specified in filter\_file. 1=apply filtering, 0=do not apply filtering. (Default for OCTS=1, Default for others=0).

### filter\_file

Directory path and filename of the filter file that contains the filter method and information to be applied to the L1B data when **filter\_opt** is set to 1. (Default=\$MSL12\_DATA/sensor/sensor\_filter.dat).

## outband\_opt

SeaWiFs out-of-band corrections. 0 = no correction, 1 = no Lw correction, 2 = full correction. (Default = 1 for SeaWiFs, 0 for all others)

## oxaband\_opt

SeaWiFs/OCTS 764nm band Oxygen correction. 0 = off, 1 = on. (Default = 1 for SeaWiFs and OCTS, 0 for others)

## glint\_opt

Correct for residual glint radiance. 0 = off, 1 = on. (Default = 0)

## aer\_opt Option for aerosol calculation mode. The default is -3.

_	Value	Description
	1	Multi-scattering with fixed model (Oceanic, 90% humidity)
	2	Multi-scattering with fixed model (Oceanic, 99% humidity)
	3	Multi-scattering with fixed model (Maritime, 50% humidity)
	4	Multi-scattering with fixed model (Maritime, 70% humidity)
	5	Multi-scattering with fixed model (Maritime, 90% humidity)
	6	Multi-scattering with fixed model (Maritime, 99% humidity)
	7	Multi-scattering with fixed model (Coastal, 50% humidity)
	8	Multi-scattering with fixed model (Coastal, 90% humidity)
	9	Multi-scattering with fixed model (Coastal, 99% humidity)
	10	Multi-scattering with fixed model (Tropospheric - 50% humidity)
	11	Multi-scattering with fixed model (Tropospheric - 90% humidity)
	12	Multi-scattering with fixed model (Tropospheric - 99% humidity)
	0	Single-scattering white aerosols (CZCS algorithm)
	-1	Multi-scattering with 765/865 model selection (default for OCTS)
	-2	Multi-scattering with 670/865 model selection (default for MOS)
	-3	Multi-scattering with 765/865 model selection and Siegel NIR iteration
	-4	Multi-scattering with 670/865 model selection and Siegel NIR iteration
	-100	Multi-scattering with 765/865 model selection and Arnone NIR iteration
	-101	Multi-scattering with 765/865 model selection and Arnone NIR (+aph) iteration
	-102	Multi-scattering with 765/865 model selection and Arnone NIR (+adg) iteration
	-103	Multi-scattering with 765/865 model selection and Arnone NIR (+aph+adg) iteration
	-110	Multi-scattering with 765/865 model selection and Arnone NIR and Stumpf 412 iteration

- -111 Multi-scattering with 765/865 model selection and Arnone NIR (+aph) and Stumpf 412 iteration
- -112 Multi-scattering with 765/865 model selection and Arnone NIR (+adg) and Stumpf 412 iteration
- -113 Multi-scattering with 765/865 model selection and Arnone NIR (+aph+adg) and Stumpf 412 iteration
- -200 Multi-scattering with 765/865 model selection and Stumpf NIR (+aph+adg)
- -201 Multi-scattering with 765/865 model selection and Stumpf NIR (+aph+adg) with 0.5% Lt412 adjustment
- -202 Multi-scattering with 765/865 model selection and Stumpf NIR (+aph+adg) with 1.0% Lt412 adjustment
- -203 Multi-scattering with 765/865 model selection and Stumpf NIR (+aph+adg) with 1.5% Lt412 adjustment
- -250 Multi-scattering with 765/865 model selection and Stumpf NIR (+aph+adg) and Stumpf 412 iteration
- -251 Multi-scattering with 765/865 model selection and Stumpf NIR (+aph+adg) and Stumpf 412 iteration with
- -252 Multi-scattering with 765/865 model selection and Stumpf NIR (+aph+adg) and Stumpf 412 iteration with
- -253 Multi-scattering with 765/865 model selection and Stumpf NIR (+aph+adg) and Stumpf 412 iteration with
- -300 Multi-scattering with 765/865 model selection and MUMM NIR

## aer\_iter\_min

The minimum number of aerosol iterations (Default = 1).

### aer iter max

The maximum number of aerosol iterations (Default = 10 for any NIR algorithm).

tau\_a Aerosol optical thickness at 865 nm for fixed model. If tau\_a > 0 and aer\_opt > 0, then the input tau a will be used to derive aerosol reflectance.

### qaa\_opt

Blending option for QAA algorithm. 0 is for blending the QAA-555 and QAA-640 absorptions and backscattering, 1 is for no blending, use QAA-555 results only, and 2 is for no blending, use QAA-670 results only.

- qaa\_S Define the S parameter to use in the QAA algorithm. Default is 0.015.
- sunzen Solar zenith angle in degrees; threshold for setting the 12\_flags bit to indicate large solar zenith angles (McClain et al., 1995). Default is 65.0.
- satzen Spacecraft zenith angle in degrees; threshold for setting the l2\_flags bit to indicate large satellite zenith angles (McClain et al., 1995). Default is 56.0.
- albedo Cloud albedo for band 8 in percent; threshold for setting the 12\_flags bit to indicate clouds or ice (McClain et al., 1995).
- absaer Absorbing aerosol threshold on aerosol index. Default is 0.5.

## glint\_thresh

Sun glint threshold (fraction of F0(865)); used in calculations for setting the 12\_flags bit to indicate sun glint (McClain et al., 1995).

#### tauamax

Maximum 865 aerosol optical depth used for setting the 12\_flags bit #5. (Default=0.3)

epsmin Minimum epsilon to trigger atmospheric correction failure flag (default is 0.65).

```
epsmax Maximum epsilon to trigger atmospheric correction failure flag (default is 1.35).
```

nlwmin Minimun nlw(555) used for setting the 12\_flags bit #15. (Default=0.15).

wsmax Windspeed limit on white-cap correction. (Default=8.0 m/s).

sl\_frac Lt 865 threshold for stray-light correction. (SeaWiFs only.) (Default = 0.25)

sl\_pixl Number of LAC pixels over which stray-light correction is applied. 0 = no correction, -1 = program defaults (8 for GAC, 3 for LAC)

## Masking keywords

These keywords select flags to be used as masks. A mask is a special flag that will cease execution on the pixel which passes the flag. For example, maskland will skip all land pixels.

## maskland

Mask out land pixels: 0=off, 1=on. (Default=1).

#### maskbath

Mask out shallow water pixels: 0=off, 1=on. (Default=0).

#### maskcloud

Mask out cloud or ice pixels: 0=off, 1=on. (Default=1).

## maskglint

Mask out sun glint pixels: 0=off, 1=on. (Default=1).

#### masksunzen

Mask out large solar zenith angle pixels: 0=off, 1=on. (Default=0).

### masksatzen

Mask out large sensor zenith angle pixels: 0=off, 1=on. (Default=0).

## maskhilt

Mask out pixels for which total radiance was greater than knee value: 0=off, 1=on. (Default=1).

## maskstlight

Mask out stray light contaminated pixels: 0=off, 1=on. (Default=1).

## **Debugging controls**

station\_input

The name of an input station file. The format is UNIX text file with three columns. The first two are the sample and line location of the desired pixel and the last is an ASCII station name field. During each iteration of the atmosopheric correction information will be dumped to an output file designated by station\_output

## station\_output

The name of an output station file. This will receive the data dumps for each station for each iteration of the atmospheric correction algorithm.

## **ENVIRONMENTAL VARIABLES**

### MSL12 DATA

Root directory for atmospheric correction data files. If this environmental variable is not set, then several ancilliary input file keywords will have to be defined. See "ANCILLIARY INPUT FILES" above.

## CAL HDF PATH

The directory and pathname of the sensor calibration file. May be undefined if **calfile** keyword has been set.

## CARDER FILE

The directory and path of the parameter file for Carder's algorithm. May be undefined if no products using Carder's algorithm have been selected.

### **EXAMPLES**

This the minimum command line execution (assumes the environmental variables have been set as shown):

```
$ export MSL12_DATA=/home/aps/aps_v2.6/data
$export CAL_HDF_PATH=$MSL12_DATA/seawifs/cal/SEAWIFS_SENSOR_CAL.TBL
$ MS112 ifile=S2000148173615.L1A_HNAV ofile1=S2000148173615.L2_HNAV
```

In this example, the user has selected to output the remote sensing reflectance data into one file, the biooptical products K\_490 and chl\_oc4 in another, and some of the Arnone IOP products in a third. It also turns off the masking of high Lt values and increases the cloud and ice threshold to 1.5.

swfL1bgen - Generate Level-1B file from Level-1A

## **SYNOPSIS**

**swfL1bgen** ifile=ifile ofile=ofile [ straylight=straylight1 ] [ outband=outband ] [ calmod\_flg=calmod\_flg ] [ calmod\_gain=calmod\_gain ] [ calmod\_off=calmod\_off ] [ calhdf=calhdf ]

– or –

swfL1bgen par=par

#### DESCRIPTION

This program reads in SeaWiFS Level-1A file (HRPT, LAC, or GAC) and generates a Level-1B file by applying the sensor calibration at the same resolution and location as the Level-1A data. The detail information about Level-1B HDF file format is available in "SeaWiFS Non-Archive Product Specification".

## **OPTIONS**

ifile Directory path and filename of the input Level–1A data product.

ofile Directory path and filename of the output Level–1B data product.

calldf Directory path and filename of the calibration table file.

# straylight

First value: if 0, stray-light correction is not applied to 11b\_data of get\_11a\_record; else, the value equals the (rounded integer) number of along-scan LAC pixels on either side of a bright target to correct 11b\_data for stray light. (For GAC data, that number is divided by four and rounded up to the nearest integer to represent the number of along-scan GAC pixels to correct.) Currently, the SeaWiFS project uses 3 for LAC and HRPT data, and 8 for GAC data. In SeaDAS, a 999 value is used for the default. In this case, the program will check the input file and use 3 for LAC and HRPT data, and 8 for GAC data.

Second value: fraction of L typical for band 8 to use as a threshold in adjacent pixels' radiance difference for detecting the edge of a bright target in the stray-light correction algorithm; ignored if first value is negative.

### outband

if 0 or negative, out-of-band correction is not applied to 11b\_data of get\_11a\_record; else, 11b\_data is the index of the out-of-band correction method to use.

## calmod\_flg

Control for calibration modification:

- 0 use gain, offset from the calibration table
- 1 use the gains from the input (calmod\_gain) and offset from the calibration table
- 2 use offsets from the input (calmod off) and the gains from the calibration table
- 3 use both gain and offset from the input (calmod\_gain & calmod\_off)

## calmod\_gain

Calibration gain factors to substitute for values read from the calibration table.

calmod\_off

Calibration gain offset factors to substitute for values read from the calibration table.

par Input parameter file to be used in the specific command mode '11bgen, par="pfile"'. The parameter file may be generated in the interactive mode and used in the command mode.

## **SEE ALSO**

swfL1agen(1) swfL2gen(1) swfCase2(1)

mosInfo - query information about a MOS Level-1A file

## **SYNOPSIS**

mosInfo [option] mosFile

### DESCRIPTION

This program is used to dump information about a MOS data file. With no options the program will print out a series of parameters. A single parameter can be single with the option. The options are succint as they were designed with shell scripting in mind.

## **OPTIONS**

```
-day Day of month of input file.
```

```
-doy Day of year of input file.
```

-hour 2-digit time (HH) of input file.

-min 2-digit time (MM) of input file.

```
-month 3-character month of input file. Months are "jan", "feb", "mar", "apr", "may", "jun", "jul", "aug", "sep", "oct", "nov", "dec"
```

-name Generate a file name in the following format as mos.YYYY.MMDD.HHMM. This is a short cut version of using -sat, -year, -doy, and -time.

-sat 3-character satellite name. Names is "mos".

-time 4-digit time (HHMM) of input file.

-type Character code for datatype: "LAC", "GAC", "HRPT"

-year 2-digit year of input file.

--version

Print out version and exit

#### **EXAMPLES**

```
$ mosInfo M1998291133955.L1A_GAC
Filename: M1998291133955.L1A_GAC
Starting Time: 10/18/1998 13:39, 291
Ending Time: 10/18/1998 14:19, 291
Satellite: mos
Datatype: GAC
Total Scans:
$
$ mosInfo -year M1998291133955.L1A_GAC
1998
```

\$

Here is how a Bourne shell script function might use **mosInfo** to set the name of the output files from:

```
set_name()
{
    sat='mosInfo -sat $1'
    yr='mosInfo -year $1'
    jday='mosInfo -doy $1'
    time='mosInfo -time $1'
    file=M$yr$jday$time.L1A_HNAV
}
```

mosScripts - standard MOS processinig scripts

## **DESCRIPTION**

mosScripts provides Bourne shell scripting functions to process MOS data from a NASA MOS Level-1B file. The mosProcess script function is the main user interface and provides for the standard processing steps. These steps are:

- 1 Verify input file is NASA MOS Level–1B file using filefmt program.
- 3 Get time information from file using mosInfo program.
- 4 Run MS112 program to atmospherically correct raw data
- For a large product array, tile and compress the data.
- 8 If user had defined \$GifList, generate browse images for selected products.
- 9 If user has defined \$MosPostProcess, it is now called. (Normally, not defined.)
- 10 Store HDF product file in the \$DATA\_BASE and the browse image in the \$IMAG\_BASE.

### **SETUP**

A minimalist executable script for processing MOS data must source both the apsScripts and mosScripts located in the APS bin directory, call the script function mosProcess passing it the name of the file name containing the MOS data and define at least two script variables. Many other variables can be optionally set to modify the *normal* mode of operations. These must be set prior to the call to mosProcess.

```
#!/bin/sh
test -z "$AUTO_DIR" && return 1
MapName=ChesapeakeBay_MOS
MapExt=GOM
mosProcess $1
```

The script must be placed in the \$AREAS\_PROC directory which is normally the directory areas located in the main APS directory. The script must have execution permissions.

## **REQUIRED VARIABLES**

These variables are required to process an area. They provide the script an area to process. Most of the remaining variables have defaults which can be overridden. They are described in the next section.

#### MapName

This is the name of the image map stored in the file \$MapFile.

## MapExt

This is a string that is appended to the Level–3 file which is written to the database. Usually it is a three character extension all uppercase.

### **OPTIONAL VARIABLES**

The following sections are variables that have defaults which the user can override to change the behaviour of the default processing. They are grouped together by subject.

## **Product Selection**

ProdList

This is a space delimetered list of products to be written to the output data base. The following products are available:

a_412_Arnone a_443_Arnone a_490_Arnone a_510_Arnone a_555_Arnone a_670_Arnone	Total Absorbtion at 412nm using Arnone Total Absorbtion at 443nm using Arnone Total Absorbtion at 490nm using Arnone Total Absorbtion at 510nm using Arnone Total Absorbtion at 555nm using Arnone Total Absorbtion at 670nm using Arnone
bb_412_Arnone	Backscattering at 412nm using Arnone
bb_443_Arnone	Backscattering at 443nm using Arnone
bb_490_Arnone	Backscattering at 490nm using Arnone
bb_510_Arnone	Backscattering at 510nm using Arnone
bb_555_Arnone	Backscattering at 555nm using Arnone
bb_670_Arnone	Backscattering at 670nm using Arnone
b_412_Arnone	Total Scattering at 412nm using Arnone
b_443_Arnone	Total Scattering at 443nm using Arnone
b_490_Arnone	Total Scattering at 490nm using Arnone
b_510_Arnone	Total Scattering at 510nm using Arnone
b_555_Arnone	Total Scattering at 555nm using Arnone
b_670_Arnone	Total Scattering at 670nm using Arnone
c_412_Arnone	Beam Attenuation at 412nm using Arnone
c_443_Arnone	Beam Attenuation at 443nm using Arnone
c_490_Arnone	Beam Attenuation at 490nm using Arnone
c_510_Arnone	Beam Attenuation at 510nm using Arnone
c_555_Arnone	Beam Attenuation at 555nm using Arnone
c_670_Arnone	Page Attanuation at 670nm using Arnona
C_070_Amone	Beam Attenuation at 670nm using Arnone
a_Arnone	Absorption for all six bands.
	-
a_Arnone	Absorption for all six bands.
a_Arnone bb_Arnone	Absorption for all six bands. Backscattering for all six bands.
a_Arnone bb_Arnone Arnone	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.
a_Arnone bb_Arnone Arnone a_412_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands. Total Absorbtion at 412nm using Carder
a_Arnone bb_Arnone Arnone a_412_Carder a_443_Carder a_490_Carder a_510_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands. Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder
a_Arnone bb_Arnone Arnone a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands. Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder
a_Arnone bb_Arnone Arnone a_412_Carder a_443_Carder a_490_Carder a_510_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands. Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder
a_Arnone bb_Arnone Arnone a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands. Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.  Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder bb_412_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.  Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder bb_412_Carder bb_443_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands. Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder Backscattering at 443nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder bb_412_Carder bb_443_Carder bb_490_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.  Total Absorbtion at 412nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder Backscattering at 490nm using Carder Backscattering at 490nm using Carder Backscattering at 510nm using Carder Backscattering at 555nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder bb_412_Carder bb_443_Carder bb_490_Carder bb_510_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands. Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder Backscattering at 443nm using Carder Backscattering at 490nm using Carder Backscattering at 510nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder bb_412_Carder bb_443_Carder bb_490_Carder bb_510_Carder bb_555_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.  Total Absorbtion at 412nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder Backscattering at 490nm using Carder Backscattering at 490nm using Carder Backscattering at 510nm using Carder Backscattering at 555nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder bb_412_Carder bb_43_Carder bb_490_Carder bb_510_Carder bb_555_Carder bb_670_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.  Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder Backscattering at 443nm using Carder Backscattering at 490nm using Carder Backscattering at 555nm using Carder Backscattering at 555nm using Carder Backscattering at 670nm using Carder Backscattering at 670nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder bb_412_Carder bb_443_Carder bb_490_Carder bb_555_Carder bb_555_Carder bb_670_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands. Total Absorbtion at 412nm using Carder Total Absorbtion at 443nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder Backscattering at 443nm using Carder Backscattering at 490nm using Carder Backscattering at 510nm using Carder Backscattering at 555nm using Carder Backscattering at 670nm using Carder Total Scattering at 412nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder  bb_412_Carder bb_443_Carder bb_490_Carder bb_555_Carder bb_670_Carder  b_412_Carder bb_412_Carder bb_510_Carder bb_412_Carder bb_510_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.  Total Absorbtion at 412nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder Backscattering at 490nm using Carder Backscattering at 555nm using Carder Backscattering at 570nm using Carder Backscattering at 470nm using Carder Total Scattering at 412nm using Carder Total Scattering at 443nm using Carder Total Scattering at 440nm using Carder Total Scattering at 450nm using Carder Total Scattering at 450nm using Carder Total Scattering at 450nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder bb_412_Carder bb_443_Carder bb_510_Carder bb_555_Carder bb_670_Carder  b_412_Carder bb_43_Carder bb_555_Carder bb_670_Carder b_443_Carder b_443_Carder b_490_Carder b_550_Carder b_550_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.  Total Absorbtion at 412nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Total Absorbtion at 412nm using Carder Backscattering at 412nm using Carder Backscattering at 490nm using Carder Backscattering at 510nm using Carder Backscattering at 555nm using Carder Total Scattering at 412nm using Carder Total Scattering at 443nm using Carder Total Scattering at 443nm using Carder Total Scattering at 440nm using Carder Total Scattering at 450nm using Carder Total Scattering at 555nm using Carder Total Scattering at 555nm using Carder Total Scattering at 555nm using Carder
a_Arnone bb_Arnone Arnone  a_412_Carder a_443_Carder a_490_Carder a_510_Carder a_555_Carder a_670_Carder  bb_412_Carder bb_443_Carder bb_490_Carder bb_555_Carder bb_670_Carder  b_412_Carder bb_412_Carder bb_510_Carder bb_412_Carder bb_510_Carder	Absorption for all six bands. Backscattering for all six bands. Absorption and Backscattering for all six bands.  Total Absorbtion at 412nm using Carder Total Absorbtion at 490nm using Carder Total Absorbtion at 510nm using Carder Total Absorbtion at 555nm using Carder Total Absorbtion at 670nm using Carder Total Absorbtion at 670nm using Carder Backscattering at 412nm using Carder Backscattering at 490nm using Carder Backscattering at 555nm using Carder Backscattering at 570nm using Carder Backscattering at 470nm using Carder Total Scattering at 412nm using Carder Total Scattering at 443nm using Carder Total Scattering at 440nm using Carder Total Scattering at 450nm using Carder Total Scattering at 450nm using Carder Total Scattering at 450nm using Carder

c_412_Carder c_443_Carder c_490_Carder c_510_Carder c_555_Carder c_670_Carder	Beam Attenuation at 412nm using Carder Beam Attenuation at 443nm using Carder Beam Attenuation at 490nm using Carder Beam Attenuation at 510nm using Carder Beam Attenuation at 555nm using Carder Beam Attenuation at 670nm using Carder
aph_412_Carder aph_443_Carder aph_490_Carder aph_510_Carder aph_555_Carder aph_670_Carder	Absorbtion due to phytoplankton at 412nm Absorbtion due to phytoplankton at 443nm Absorbtion due to phytoplankton at 490nm Absorbtion due to phytoplankton at 510nm Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm
adg_412_Carder adg_443_Carder adg_490_Carder adg_510_Carder adg_555_Carder adg_670_Carder	Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm Absorbtion due to detritis and gelbstuff at 490nm Absorbtion due to detritis and gelbstuff at 510nm Absorbtion due to detritis and gelbstuff at 555nm Absorbtion due to detritis and gelbstuff at 670nm
chlor_a_Carder a_Carder adg_Carder aphi_Carder bb_Carder	Chlorophyll-a concentration  Absorption for all six bands.  Absorption due to detritis and gelbstuff for all six bands.  Absorption due to phytoplankton for all six bands.  Backscattering for all six bands.
Carder  rrs_412 rrs_443 rrs_490 rrs_510 rrs_555 rrs_670	Same as ProdList="a_Carder adg_Carder aphi_Carder bb_Carder chlor_a_Carder"  Remote Sensing Reflectance at 412 Remote Sensing Reflectance at 443 Remote Sensing Reflectance at 490 Remote Sensing Reflectance at 510 Remote Sensing Reflectance at 555 Remote Sensing Reflectance at 670
rrs_765 rrs_865 K_490_SeaDAS K_532_SeaDAS chlor_a_SeaDAS	Remote Sensing Reflectance at 765 Remote Sensing Reflectance at 865  Diffuse Attenuation at 490nm using 443/555 Diffuse Attenuation at 532nm using 490/555  Chlorophyll—a concentration using OC2
chlor_a_Stumpf pigments_SeaDAS 12_flags tau_865 epsilon albedo_865	Chlorophyll—a concentration using Stumpf Pigments Flags Tau at 865 nm Epsilon Percent albedo at 865nm
glint_865 foam_865 latitude	Glint at 865 nm Foam at 865 nm Latitude

Longitude

longitude

solar_zenith	Solar Zenith Angle
solar_azimuth	Solar Azimuth Angle
sat_zenith	Satellite Zenith Angle
sat_azimuth	Satellite Azimuth Angle
	_
adg_412_Stumpf	Absorption due to Gelbstoff
aphi_443_Stumpf	Absorption due to Phytoplankton
a_555_Stumpf	Total Absorption at 555
a_412_Stumpf	Total Absorption at 412
adg_555_Stumpf	Absorption due to Gelbstoff
Rt_412	Total Reflectance at 412
Rt_443	Total Reflectance at 443
Rt_490	Total Reflectance at 490
Rt_510	Total Reflectance at 510
Rt_555	Total Reflectance at 555
Rt_670	Total Reflectance at 670
Rt_765	Total Reflectance at 765
Rt_865	Total Reflectance at 865
D 440	B 111 B 2
Rr_412	Rayleigh Reflectance at 412
Rr_443	Rayleigh Reflectance at 443
Rr_490	Rayleigh Reflectance at 490
Rr_510	Rayleigh Reflectance at 510
Rr_555	Rayleigh Reflectance at 555
Rr_670	Rayleigh Reflectance at 670
Rr_765	Rayleigh Reflectance at 765
Rr_865	Rayleigh Reflectance at 865
Ra_412	Aerosol Reflectance at 412
Ra_443	Aerosol Reflectance at 443
Ra_490	Aerosol Reflectance at 490
Ra_510	Aerosol Reflectance at 510
Ra_555	Aerosol Reflectance at 555
Ra_670	Aerosol Reflectance at 670
Ra_765	Aerosol Reflectance at 765
Ra_865	Aerosol Reflectance at 865
111_000	Tierosof Reneemiee at 605
zone_w	Zonal Winds
merid_w	Meridian Winds
humidity	Humidity
pressure	Pressure
ozone	Ozone

# Name all desired products

For example, at NRL we process the 33 products for each scene. Here is how the product list is defined in our script SwfGulfofMexico.

```
ProdList="rrs_412 rrs_443 rrs_490 rrs_510 rrs_555 rrs_670"
ProdList="$ProdList K_532_Mueller albedo_865 l2_flags"
ProdList="$ProdList chlor_a_SeaDAS chlor_a_Stumpf"
ProdList="$ProdList chlor_a_Carder"
ProdList="$ProdList a_Arnone"
```

```
ProdList="$ProdList a_Carder"
ProdList="$ProdList adg_412_Carder aph_443_Carder"
ProdList="$ProdList adg_412_Stumpf aph_443_Stumpf"
ProdList="$ProdList bb_443_Arnone bb_555_Arnone"
ProdList="$ProdList bb_443_Carder bb_555_Carder"
ProdList="$ProdList c_670_Carder"
```

Region This variable will be used to create the default data base directories. By default it set to \$Map-

### MosDataBase

This variable is used to indicate the location of the image data base for the generated product file. By default, it is set to:

\$DataBase/\$Level/\$Sensor/\$Version/\$Region/\$Year/\$Month.

#### where.

\$DataBase is defined in the aps.conf file and represents the top directory of the data base. \$Level is set to the string "lvl3" by mosInit. \$Sensor is set to the string "mos" by mosInit. \$Version is set to "2.4" by mosInit. \$Region is set to "\$MapName" by mosInit. \$Year and \$Month are set by mosProcess based on the input file.

The user can override \$SwfDataBase since it is evaluated by the shell prior to use. For example, if the line:

```
SwfDataBase="\$DataBase/seawifs/\$Year"
```

is set in the areas script and we assume that \$DataBase is set to /data and that for a particular file \$Year has been set to 1999, then the product file will be moved to /data/seaw-ifs/1999. Note that to use the variables, the user must "escape" the '\$' by inserting a "\".

## CmpOpt

This can be defined by the user to select the type of compression program to call for the output product file before it is moved to \$SwfDataBase. This option can be set to: "gzip", "compress", "bzip2" or "none". Only set CmpOpt to a compression type that is available on user's machine. *Note:* If the user has defined XNumChunks or that variable is defined by mosInit, then the HDF file will automatically be internally compressed and this variable will have no effect.

## mosDebug

If defined this variable will cause the script functions to call 'set -x' within each script function. This will have the effect of printing out each step as it is executed.

## MapFile

Name of file containing image map file. Defaults to \$AutoData/maps.hdf

## MinPixels, MinLines

Used to set the minimum pixels/lines that must be extracted from the MOS file by swfExtract to continue processing. These are used to insure that enough of the input file covers the area of interest. By default these are not defined and, therefore, no check is performed.

### XNumChunks, YNumChunks

These are used to define the number of "chunks" in each direction which will be created by imgReformat program for the product files. By default, a large level–3 file will be rewritten in chunks (or "tiles") with each chunk being compressed. A chunk will be no larger than 640 by 640. So, if the map image is 2430 by 1810, then imgReformat will create a total of 12 chunks (4 across and 3 down). A 1500 by 1500 map image will be divided into 9 chunks (3 across and 3 down). A 600 by 300 map image will NOT be chunked.

FileExt Optional extension to L2 files which can be used to prevent filename clashes. Normally, not defined.

## **MOS Processing Parameters**

CalFile Name of calibration file to be used during Level-2 processing. Defaults to \$AUTO\_DATA/seaw-ifs/SEAWIFS\_SENSOR\_CAL.TBL-199909-time\_dep\_7jun99.

### LandMask

Name of landmask file to be used during Level-2 processing. Defaults to \$AutoData/seaw-ifs/landmask.dat

#### WaterMask

Name of watermask file to be used during Level-2 processing. Defaults to \$AutoData/seaw-ifs/watermask.dat

### MosAtmOpts

This controls the atmospheric algorithm used. By default, it is set to "stumpf". It can also be removed to get the default atmospheric correction. If set to "arnone", then the Arnone NIR iteration alone is run. If "aphi" is added, for example, <code>SwfAtmOpts="arnone aphi"</code> then the Arnone NIR iteration with the aphi adjustment is run. The "aphi" option will have not effect if added to stumpf or run on its own. You can use both "stumpf" and "arnone" at the same time.

## MosParamFile

Name of file containing additional options to the MS112 program. These should *not* contain the following options: par=, in=, out=, outqc=, calhdf= (use CalFile instead), landmask= (use Land-Mask instead), watermask= (use WaterMask instead), met1=, met2=, met3= (use SwfMetDir, SwfMetFile instead), ozone1=, ozone2=, ozone3= (use SwfOzoneDir, SwfOzoneFile instead). All others should present no problems. The user's options located in the file pointed to by SwfParam-File are appended the to parameter file automatically generated by swfScripts.

### MosOzoneDir, MosOzoneFile

Normally, these are undefined and will cause the climatology ozone file located in the data/seawifs directory to be used.

To use the NRT ozone data, the user must download it from the Goddard DAAC. The variable MosOzoneDir points to the location of the NRT ozone file(s). If MosOzoneFile is not set, then swfNRL will use the input file's date to build the appropriate file name. If this file had been compressed using gzip or compress, it is uncompressed. If MosOzoneFile is set, it must be an uncompressed file -- swfNRL sends it straight to l2gen, which will die if the file is incorrect.

If MosOzoneDir is undefined, or the file \$MosOzoneDir/\$MosOzoneFile is not a regular file, then climatology file will be used.

### MosMetDir, MosMetFile

Like MosOzoneDir and MosOzoneFile defined above but for the MET data.

## **Browse Image Variables**

GifList This is a list of whitespace delimetered products which are converted to browse images. The products in this list must also be present in the \$ProdList variable. By default, no browse images are created. That is, GifList is not defined.

GifDir This variable is used to indicate the location of for the browse images. By default, it is set to:

\$ImagBase/\$Level/\$Sensor/\$Version/\$Region/\$Year/\$Month.

#### where,

\$ImagBase is set in the aps.conf file and represents the top directory of the browse data base. \$Level is set to the string "lvl3" by mosInit.

\$Sensor is set to the string "mos" by mosInit.

\$Version is set to "2.4" by mosInit.

\$Region is set by the user in the area script.

\$Year and \$Month are set by mosProcess based on the input file.

The user can override \$GifDataBase since it is evaluated by the shell prior to use. For example, if the line:

```
GifDataBase="\$ImagBase/browse/\$Year"
```

is set in the areas script and we assume that \$ImagBase is set to /data and that for a particular file \$Year has been set to 1999, then the browse image will be moved to /data/browse/1999.

### \${prod} GifScaling

It defines the user's desired output scaling for the browse images. For example, to produce an chlorophyll–a browse image that is 300 pixels by 400 lines and has a data range from 0.01 to 10.0 using a log10 scale, add the line:

```
chlor_a_SeaDAS_GifScaling="-f log10 -r 0.01,10.0 -R 20,199 -s 300,400"
```

in the areas script. See **imgBrowse**(1) for more information. *Note:* The output range is set to 20 and 199 because the swfMakeGif file script uses NSIPS files for overlays and colortables by default.

By default, the following scaling is defined by swfScripts.

channel	function	min	max
rrs_412	linear	-0.005	0.015
rrs_443	linear	-0.005	0.015
rrs_490	linear	-0.005	0.015
rrs_510	linear	-0.005	0.015
rrs_555	linear	-0.005	0.015
rrs_670	linear	-0.005	0.015
rrs_765	linear	-0.005	0.015
rrs_865	linear	-0.005	0.015
K_490_SeaDAS	log10	0.01	2.0
K_532_SeaDAS	log10	0.02	2.0

K_532_Mueller	log10	0.01	2.0
pigments_SeaDAS	log10	0.01	64.0
chlor_a_Carder	log10	0.01	45.0
chlor_a_SeaDAS	log10	0.01	45.0
chlor_a_Stumpf	log10	0.01	15.0
aph_443_Stumpf	log10	0.002	1.0
adg_412_Stumpf	log10	0.001	10.0
adg_555_Stumpf	log10	0.0001	0.0175
a_412_Stumpf	log10	0.01	1.5
a_555_Stumpf	log10	0.01	1.5
<u> </u>	10810	0.01	110
a_412_Arnone	log10	0.005	1.5
a_443_Arnone	log10	0.001	2.0
a_490_Arnone	log10	0.005	1.5
a_510_Arnone	log10	0.005	1.5
a_555_Arnone	log10	0.005	1.5
a_670_Arnone	linear	0.4	0.9
a_765_Arnone	linear	0.4	4.3
bb_412_Arnone	log10	0.0005	0.5
bb_443_Arnone	log10	0.0005	0.5
bb_490_Arnone	log10	0.0005	0.5
bb_510_Arnone	log10	0.0005	0.5
bb_555_Arnone	log10	0.0005	0.3
bb_670_Arnone	log10	0.0005	0.5
bb_765_Arnone	log10	0.0005,0.5	0.5
bb_/bb_Afficile	logio	0.0003,0.3	
a_412_Carder	log10	0.01	1.5
a_443_Carder	log10	0.01	1.5
a_490_Carder	log10	0.01	1.5
a_510_Carder	log10	0.01	1.5
a_555_Carder	log10	0.01	1.5
a_670_Carder	log10	0.01	1.5
aph_412_Carder	log10	0.00005	0.5
aph_443_Carder	log10	0.001	1.0
aph_490_Carder	log10	0.00005	0.5
aph_510_Carder	log10	0.00005	0.5
aph_555_Carder	log10	0.00005	0.5
aph_670_Carder	log10	0.00005	0.5
adg_412_Carder	log10	0.010	1.0
adg_443_Carder	-	0.010	0.5
adg_490_Carder	log10 log10	0.003	0.3
adg_490_Carder adg_510_Carder	log10	0.001	0.18
adg_510_Carder adg_555_Carder	log10	0.0007	0.12
	-		
adg_670_Carder	log10	0.00001	0.00175
bb_412_Carder	log10	0.0005	0.5
bb_443_Carder	log10	0.0005	0.5
bb_490_Carder	log10	0.0005	0.5

bb_510_Carder	log10	0.0005	0.5
bb_555_Carder	log10	0.0005	0.2
bb 670 Carder	log10	0.0005	0.5

*Note:* For the other products (those list in ProdList above but not here), the user must provide the corresponding variables as there are no defaults.

## \${prod}\_Overlay

To apply an overlay, the user may set this variable. By default, it is defined to be \$Auto-Data/areas/\$MapName/w\_\${Sensor}\_\$prod.pic. This file is overlayed over the image file. See **nsOverlay**(1) for more information.

## GifLabelOpts, \${prod} GifLabelOpts, and \${prod} GifLabel

To add a label, the user must define at least GifLabelOpts. This will consist of three space delimetered values containing the x-location, y-location, and color index of the label. For an individual product, the user may define  ${\text{prod}}_{GifLabelOpts}$ . If not defined, it will default to GifLabelOpts. The label to be written at that location is defined by  ${\text{prod}}_{GifLabel}$ . If not defined, it will default to " ${\text{month}}_{Sigh}$ "

For example, suppose the following lines are in the "areas" script:

```
GifList="chlor_a_SeaDAS K_490_SeaDAS"
GifLabelOpts="20 30 3"
chlor_a_SeaDAS_GifLabelOpts="40 32 4"
```

In this example, the user has requested that the chlor\_a\_SeaDAS and K\_490\_SeaDAS browse images be generated. Each will have the default label written to it. The chlor\_a\_SeaDAS product will have the label written at (20,30) using color index 3 while the K\_490\_SeaDAS product will have the label written at (40,32) using color index 4.

### \${prod}\_GifColorTable

The colortable used can be set by defining this variable. If not set, then it will default to \$Auto-Data/color/ct\_\$prod.ct. If that file is not found or is unreadable, then it will default to a linear colortable.

### ImgSamples and ImgLines

These are used to override the default sizes of the browse images. By default, these values will be calculated such that the browse image will be a integral zoom factor smaller than the original image that will be smaller than 640 by 640. For example, if the map size is 600 by 300, then the browse image will be 600 by 300. If the map size is 2430 by 1810, then the browse image will be 640 by 476. If the map size is 1500 by 1500, then the browse image will be 640 by 640.

### **Program Variables**

These variables define the programs used by swfScripts. The user can overide these to test a new version of a program. They are defined in swfInit.

## ApsInfo

Set to the name of the satellite specific program used to obtain information from input Level-1 file. Defaults to \$AutoBin/swfInfo.

MS112 Set to the name of the program used to do the atmospheric correction and generate the remote sensing reflectance products. Defaults to \$AutoBin/swfCase2.

## MosInfo

Set to the name of the program used to obtain information from MOS file. Defaults to \$Auto-Bin/swfInfo.

## **CONFORMANCE**

These script functions attempt to conform to the IEEE 1003.2 POSIX Shell Standard. They were, however, developed and tested using the Bourne Shell and Korn Shells under IRIX 5.3 and IRIX 6.5 respectively.

## **SEE ALSO**

 $apsScripts(1) \ daylight(1), \ filefmt(1), \ hdf(1), \ maps(1), \ nsDabel(1), \ nsOverlay(1), \ nsPicToGIF(1), \\ imgMap(1), imgReformat(1), imgBrowse(1), imgSDStoImg(1), mosInfo(1), mosCase2(1), \\$ 

swfArea - determine file extents of geographical area

### **SYNOPSIS**

swfArea [-M mapFile] mapName inFile

### DESCRIPTION

Determine the file extents (start/stop pixel/line) of a SeaWiFS file (still in sensor projection, i.e. L1A, L2, etc.) that covers a map.

**SwfArea** begins by reading in the map from the mapFile. If the file can not be opened or the named map is not in the file, a diagnostic is printed and the program will exit.

Next, the SeaWiFS file is opened and the navigation information initialized. If unable to open the SeaWiFS file or retrieve the navigation information from it, the program will print a diagnostic and exit. The navigation to be read includes the SDS arrays "orb\_vec", "scan\_ell", "sen\_mat", and "tilt".

Once the navigation has been set, **swfArea** reads in every 64th scan line, and using every 64th sample, determines if that point falls within the desired map. From this, the smallest box (modulo 64) that will cover the box will be determined. These file extents will be printed to the screen.

If the 64-sided box fails or the user has selected a refined coverage, **swfArea** will rescan the entire image (if 64-sides failed) or the box determined previously (if user selected refined coverage) using a small 5-sided box. If the file extents are found they are printed or the message "No coverage." If the file extents are the original input file, then the message will be "Complete coverage."

A third pass, which may be quite computer intensive, uses a reverse mapping to determine the file extents. It scans through the entire map image to determine where that pixel lies in the SeaWiFS file. For large map areas this computation can require large resources (i.e. memory and CPU time). The user can select this pass directly by using the exact option (-e) or allow it to be used after the first two passes have failed (-3).

## **OPTIONS**

- -e Do a reverse mapping from the map to the SeaWiFS file to determine its file extents. May be more computer intensive depending on the selected map.
- -l Don't output start/stop line locations
- -M mapFile

Use the given map file to find mapName. Defaults to \$AUTO\_DATA/maps.hdf

- -p Don't output start/stop pixel locations
- -r Refine search to within plus or minus 5 samples/lines.
- -v Make output verbose.
- -3 If passes one and two fail, use pass 3. This is mainly useful for maps that are smaller than the 5-sided box. (Why use SeaWiFS, then?)

--version

Print out version and exit.

## **ENVIRONMENTAL VARIABLES**

AUTO\_DATA

The location of the APS data directory.

## **EXAMPLES**

```
$ swfArea -M maps.hdf MissBight S2000144175835.L1A_HNAV
257 835 1793 2177
$ swfArea -M maps.hdf EastSea S2000144175835.L1A_HNAV
No coverage
$ export AUTO_DATA=/usr/local/aps/data
$ swfArea MissBight S2000144175835.L1A_HNAV
257 835 1793 2177
$ swfArea -r MissBight S2000144175835.L1A_HNAV
301 783 1849 2177
```

## **SEE ALSO**

**MSl12**(1)

swfArnone – creates images of inherent optical properities

## **SYNOPSIS**

**swfArnone** [options] inFile [ouFile]

### DESCRIPTION

The swfArnone program will generate inherent optical properties using the Arnone algorithm. The input file must be an HDF file with the SDSs, "rrs\_412", "rrs\_443", "rrs\_490", "rrs\_510", "rrs\_555", "rrs\_670", and "rrs\_765", which represent the remote sensing reflectances at 412, ..., 765 nm. By default, the input remote sensing reflectances are used to estimate the chlorophyll concentration using the SeaBAM (OC2 v2) algorithm, however, the user can request to use another input chlorophyll image using the –c option.

By default, twelve output products, six total absorption and six backscattering at the SeaWiFS wavelengths of 412, 443, 490, 510, 555, 670, are written back to the input file as SDS's using the following nomenclature "a\_XXX\_arnone" and "bb\_XXX\_arnone", where "XXX" is replaced by the above values. Optionally, the user may request the difference product of the total absorption at 443 minus the total absorption at 412, as well as, total scattering and beam attenuation products at all six wavelengths.

### **OPTIONS**

- -a A bit-field representing flags for selecting one of the 6 possible total absorption outputs. For example, "-a 5" will select only the a\_412 and a\_490 products.
- -b A bit-field representing flags for selecting one of the 6 possible backscatter outputs. For example, "-b 16" will select only the bb\_555 product.
- -B A bit-field representing flags for selecting one of the 6 possible total scattering outputs. For example, "-B 16" will select only the b\_555 product. The nomenclature for these SDS's are "b\_XXX\_arnone".
- -C A bit-field representing flags for selecting one of the 6 possible beam attenuation outputs. For example, "-B 9" will select only the c\_412 and c\_510 product. The nomenclature for these SDS's are "c\_XXX\_arnone".
- -c Name of input SDS containing chlorophyll-a data. This option is used to specify an input chlorophyll-a image. Otherwise, the input remote sensing reflectances are used with the SeaBAM chlorophyll algorithm to estimate the chlorophyll concentration.
- -d Select the a\_443 a\_412 difference image for output. This SDS is called "adiff\_arnone".
- -r The nomenclature for the eight input remote sensing reflectance SDSs. The characters XXX will be replaced by the three digits representing the wavelengths. For example, "-r rrs\_XXX" will select remote sensing reflectance arrays: "rrs\_412", "rrs\_443", etc. (currently unimplemented)
- -v Verbose
- --version

Print out version and exit.

# REFERENCES

The Arnone algorithm is unpublished.

## **EXAMPLES**

The following example appends twelve products  $(a\_XXX)$  and  $bb\_XXX$  for the first six SeaWiFS wavelengths to the input file.

```
$ swfArnone rrs.hdf
```

In this example the output file, "test.hdf", the total absorption at 412 nm, total scattering at 555 nm and beam attenuation at 670 nm, are created.

```
$ swfArnone -a 1 -B 16 -C 32 rrs.hdf test.hdf
```

## **SEE ALSO**

MSl12(1), swfCarder(1)

swfCarder - create images of inherent optical properities

## **SYNOPSIS**

**swfCarder** [options] inFile [ouFile]

### DESCRIPTION

The swfCarder program will generate inherent optical properties using the Carder algorithm. This algorithm calculates aph675 and ag400 algebraically from Rrs model equations. Chlorophyll—a is then calculated from aph675. The input file must be an HDF file with the SDSs, "rrs\_412", "rrs\_443", "rrs\_490", "rrs\_510", "rrs\_555", and "rrs\_670", which represent the remote sensing reflectances at 412, ..., 670 nm.

By default, twenty-five output products, six total absorption, six backscattering, six photoplankton absorption, and six detris/gelbstuff absorption at the SeaWiFS wavelengths of 412, 443, 490, 510, 555, 670 and a chlorophyll-a product, are written back to the input file as SDS's using the following nomenclature "a\_XXX\_carder", "bb\_XXX\_carder", "aph\_XXX\_carder", "adg\_XXX\_carder" and "chlor\_a\_carder" where "XXX" is replaced by the above values. Optionally, the user can request the total scattering and beam attenuation products at all six wavelengths.

### **OPTIONS**

- -a A bit-field representing flags for selecting one of the 6 possible total absorption outputs. For example, "-a 5" will select only the a\_412 and a\_490 products.
- -b A bit-field representing flags for selecting one of the 6 possible backscatter outputs. For example, "-b 16" will select only the bb\_555 product.
- -B A bit-field representing flags for selecting one of the 6 possible total scattering outputs. For example, "-B 16" will select only the b\_555 product. The nomenclature for these SDS's are "b\_XXX\_carder".
- -c Flag to output the chlorophyll-a data. This SDS will be named "chlor\_a\_carder".
- -C A bit-field representing flags for selecting one of the 6 possible beam attenuation outputs. For example, "-B 9" will select only the c\_412 and c\_510 product. The nomenclature for these SDS's are "c XXX carder"
- -g A bit-field representing flags for selecting one of the 6 possible detris and gelbustuf absorption outputs. For example, "-g 17" will select the adg 412 and adg 555 products.
- -p A bit-field representing flags for selecting one of the 6 possible phytoplankton absorption outputs. For example, "-p 7" will select only the aph\_412, aph\_443, and aph\_490 products.
- -s Do iteration on the "s" term.
- -v Turn on verbose output.
- --version

Print out version and exit.

## **REFERENCES**

Carder et al., Reflectance model for quantifying chlorophyll—a in the presence of productivity degradation products, JGR, 96(C11), 20599-20611, 1991.

Lee et al., Model for the interpretation of hyperspectral remote sensing reflectance, Appl. Opt, 33(24), 5721, 1994.

## **EXAMPLES**

The following example appends twenty-five products (a\_XXX\_carder, aph\_XXX\_carder, adg\_XXX\_carder, bb\_XXX\_carder, and chlor\_a\_carder) for the first six SeaWiFS wavelengths to the input file.

```
$ swfCarder rrs.hdf
```

In this example the output file, "test.hdf", the total absorption at 412 nm, total scattering at 555 nm and beam attenuation at 670 nm, are created.

```
$ swfCarder -a 1 -g 0 -p 0 -B 16 -c -C 32 rrs.hdf test.hdf
```

## **SEE ALSO**

MSl12(1), swfArnone(1)

swfGetElements – download elements.dat file from NASA/GSFC

## **SYNOPSIS**

swfGetElements

## **DESCRIPTION**

The script **swfGetElements** is used to automatically retreive the elements.dat file needed by the swfL1AGen program. It is called from with swfScripts. This script *requires* the GNU wget package.

## **OPTIONS**

--version

Print out version and exit.

## **DIAGNOSITCS**

If the \$AUTO\_DATA/seawifs/swfmops directory does not exist or lacks user write permissions, the script will fail. If the wget program fails, a copy of the download will be printed to stdout.

## **SEE ALSO**

 $\mathbf{swfL1AGen}(1), \mathbf{swfScripts}(1)$ 

swfInfo - query information about a SeaWiFS Level-1A file

## **SYNOPSIS**

swfInfo [option] swfFile

### DESCRIPTION

This program is used to dump information about a SeaWiFS data file. With no options the program will print out a series of parameters. A single parameter can be single with the option. The options are succint as they were designed with shell scripting in mind.

### **OPTIONS**

```
-day Day of month of input file.
```

```
-doy Day of year of input file.
```

-hour 2-digit time (HH) of input file.

-min 2-digit time (MM) of input file.

```
-month 3-character month of input file. Months are "jan", "feb", "mar", "apr", "may", "jun", "jul", "aug", "sep", "oct", "nov", "dec"
```

-name Generate a file name in the following format as swf.YYYY.MMDD.HHMM. This is a short cut version of using -sat, -year, -doy, and -time.

-sat 3-character satellite name. Names is "swf".

-time 6-digit time (HHMMSS) of input file.

-type Character code for datatype: "LAC", "GAC", "HRPT"

-year 2-digit year of input file.

--version

Print out version and exit.

#### **EXAMPLES**

\$

Here is how a Bourne shell script function might use **swfInfo** to set the name of the output files from the input file:

```
set_name()
{
    sat='swfInfo -sat $1'
    yr='swfInfo -year $1'
    jday='swfInfo -doy $1'
    time='swfInfo -time $1'
    file=S$yr$jday$time.L1A_HNAV
}
```

swfMail – mail filter for transfer of Level–1A data to Goddard

# **SYNOPSIS**

swfMail

## **DESCRIPTION**

The swfMail program is used to filter the mail communication that occurs between the receiving station and Goddard.

swfScripts - standard SeaWiFS processinig scripts

## **DESCRIPTION**

swfScripts provides Bourne shell scripting functions to process SeaWiFS data from a NASA SeaWiFS Level-1A file. The swfProcess script function is the main user interface and provides for the standard processing steps. These steps are:

- 1 Initialize variables, check for programs, etc
- 2 Verify input file is NASA SeaWiFS Level–1A file using filefmt program.
- 3 Determine if file covers user defined map using swfArea program.
- 4 Get time information from file using swfInfo program.
- 5 Create parameter file for MS112
- 6 Optionally, add daily ancillary data
- 7 Run MS112 program to atmospherically correct Level–1 data (Level–2)
- 8 Warp Level-2 file to Level-3 using imgMap
- 9 If user had defined L3BrowseList, generate browse images for selected products.
- 10 If user has defined SwfPostProcess, it is now called. (Normally, not defined.)
- 11 If user has define TSProd, generate time series
- 12 Store HDF product file in the DATA\_BASE and the browse image in the IMAG\_BASE.
- 13 Generate Level-4 data adding in this new Level-3 file.

#### **SETUP**

A minimalist executable script for processing SeaWiFS data must source both the apsScripts and swfScripts located in the APS bin directory, call the script function swfProcess passing it the name of the file name containing the SeaWiFS data and define at least two script variables. Many other variables can be optionally set to modify the normal mode of operations. These must be set prior to the call to swfProcess.

```
#!/bin/sh
test -z "$AUTO_DIR" && return 1
AUTO_BIN=${AUTO_BIN:=AUTO_DIR/bin}
MapName=ChesapeakeBay
swfProcess $1 $0
```

The script must be placed in the \$AREAS\_PROC directory which is normally the directory areas located in the main APS directory. The script must have execution permissions.

## **REQUIRED VARIABLES**

These variables are required to process an area. They provide the script an area to process. Most of the remaining variables have defaults which can be overridden. They are described in the next section.

MapName

This is the name of the image map stored in the file \$MapFile.

## **OPTIONAL VARIABLES**

The following sections are variables that have defaults which the user can override to change the behaviour of the default processing. They are grouped together by subject.

## **Product Selection**

This is probably the first thing that anyone will want to change. By default, the SeaWiFS list of products both Level-3 and Level-4 are defined in a UNIX text files. Similar the default browse images are also defined. The user can override these list of products in several ways.

First the use can actually modify the data files directly, or use the variables L3ProdFile, L3ProdList, L4ProdFile, orL4ProdList. Any any case, the user can select from any of the products listed below. Also, if a product is listed as a Level-4 product, it must also be listed as a Level-3 product.

## **Arnone IOP Products**

a_412_arnone	Total Absorbtion at 412nm using Arnone
a_443_arnone	Total Absorbtion at 443nm using Arnone
a_490_arnone	Total Absorbtion at 490nm using Arnone
a_510_arnone	Total Absorbtion at 510nm using Arnone
a_555_arnone	Total Absorbtion at 555nm using Arnone
a_670_arnone	Total Absorbtion at 670nm using Arnone
bb_412_arnone	Backscattering at 412nm using Arnone
bb_443_arnone	Backscattering at 443nm using Arnone
bb_490_arnone	Backscattering at 490nm using Arnone
bb_510_arnone	Backscattering at 510nm using Arnone
bb_555_arnone	Backscattering at 555nm using Arnone
bb_670_arnone	Backscattering at 670nm using Arnone
b_412_arnone	Total Scattering at 412nm using Arnone
b_443_arnone	Total Scattering at 443nm using Arnone
b_490_arnone	Total Scattering at 490nm using Arnone
b_510_arnone	Total Scattering at 510nm using Arnone
b_555_arnone	Total Scattering at 555nm using Arnone
b_670_arnone	Total Scattering at 670nm using Arnone
c_412_arnone	Beam Attenuation at 412nm using Arnone
c_443_arnone	Beam Attenuation at 443nm using Arnone
c_490_arnone	Beam Attenuation at 490nm using Arnone
c_510_arnone	Beam Attenuation at 510nm using Arnone
c_555_arnone	Beam Attenuation at 555nm using Arnone
c_670_arnone	Beam Attenuation at 670nm using Arnone

# **Carder IOP Products**

a_412_carder	Total Absorbtion at 412nm using Carder
a_443_carder	Total Absorbtion at 443nm using Carder
a_490_carder	Total Absorbtion at 490nm using Carder
a_510_carder	Total Absorbtion at 510nm using Carder
a_555_carder	Total Absorbtion at 555nm using Carder
a_670_carder	Total Absorbtion at 670nm using Carder
bb_412_carder	Backscattering at 412nm using Carder
bb_443_carder	Backscattering at 443nm using Carder
bb_490_carder	Backscattering at 490nm using Carder
bb_510_carder	Backscattering at 510nm using Carder
bb_555_carder	Backscattering at 555nm using Carder
bb_670_carder	Backscattering at 670nm using Carder
b_412_carder	Total Scattering at 412nm using Carder
b_443_carder	Total Scattering at 443nm using Carder
b_490_carder	Total Scattering at 490nm using Carder
b_510_carder	Total Scattering at 510nm using Carder
b_555_carder	Total Scattering at 555nm using Carder
b_670_carder	Total Scattering at 670nm using Carder
c_412_carder	Beam Attenuation at 412nm using Carder
c_443_carder	Beam Attenuation at 443nm using Carder
c_490_carder	Beam Attenuation at 490nm using Carder
c_510_carder	Beam Attenuation at 510nm using Carder
c_555_carder	Beam Attenuation at 555nm using Carder
c_670_carder	Beam Attenuation at 670nm using Carder
aph_412_carder	Absorbtion due to phytoplankton at 412nm
aph_443_carder	Absorbtion due to phytoplankton at 443nm
aph_490_carder	Absorbtion due to phytoplankton at 490nm
aph_510_carder	Absorbtion due to phytoplankton at 510nm
aph_555_carder	Absorbtion due to phytoplankton at 555nm
aph_555_carder aph_670_carder	
aph_670_carder	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm
aph_670_carder adg_412_carder	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm Absorbtion due to detritis and gelbstuff at 412nm
aph_670_carder adg_412_carder adg_443_carder	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm
aph_670_carder adg_412_carder adg_443_carder adg_490_carder	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm Absorbtion due to detritis and gelbstuff at 490nm
aph_670_carder adg_412_carder adg_443_carder adg_490_carder adg_510_carder	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm Absorbtion due to detritis and gelbstuff at 490nm Absorbtion due to detritis and gelbstuff at 510nm
aph_670_carder adg_412_carder adg_443_carder adg_490_carder	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm Absorbtion due to detritis and gelbstuff at 490nm

# **QAA IOP Products**

a_412_qaa	Total Absorbtion at 412nm using Carder
a_443_qaa	Total Absorbtion at 443nm using Carder
a_490_qaa	Total Absorbtion at 490nm using Carder
a_510_qaa	Total Absorbtion at 510nm using Carder
a_555_qaa	Total Absorbtion at 555nm using Carder
a_670_qaa	Total Absorbtion at 670nm using Carder
_	_
bb_412_qaa	Backscattering at 412nm using Carder
bb_443_qaa	Backscattering at 443nm using Carder
bb_490_qaa	Backscattering at 490nm using Carder
bb_510_qaa	Backscattering at 510nm using Carder
bb_555_qaa	Backscattering at 555nm using Carder
bb_670_qaa	Backscattering at 670nm using Carder
_	
b_412_qaa	Total Scattering at 412nm using Carder
b_443_qaa	Total Scattering at 443nm using Carder
b_490_qaa	Total Scattering at 490nm using Carder
b_510_qaa	Total Scattering at 510nm using Carder
b_555_qaa	Total Scattering at 555nm using Carder
b_670_qaa	Total Scattering at 670nm using Carder
c_412_qaa	Beam Attenuation at 412nm using Carder
c_443_qaa	Beam Attenuation at 443nm using Carder
c_490_qaa	Beam Attenuation at 490nm using Carder
c_510_qaa	Beam Attenuation at 510nm using Carder
c_555_qaa	Beam Attenuation at 555nm using Carder
c_670_qaa	Beam Attenuation at 670nm using Carder
aph_412_qaa	Absorbtion due to phytoplankton at 412nm
aph_443_qaa	Absorbtion due to phytoplankton at 443nm
aph_490_qaa	Absorbtion due to phytoplankton at 490nm
anh 510 ann	
aph_510_qaa	Absorbtion due to phytoplankton at 510nm
aph_555_qaa	Absorbtion due to phytoplankton at 555nm
	* * *
aph_555_qaa aph_670_qaa	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm
aph_555_qaa aph_670_qaa adg_412_qaa	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm
aph_555_qaa aph_670_qaa adg_412_qaa adg_443_qaa	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm
aph_555_qaa aph_670_qaa adg_412_qaa adg_443_qaa adg_490_qaa	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm Absorbtion due to detritis and gelbstuff at 490nm
aph_555_qaa aph_670_qaa adg_412_qaa adg_443_qaa adg_490_qaa adg_510_qaa	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm Absorbtion due to detritis and gelbstuff at 490nm Absorbtion due to detritis and gelbstuff at 510nm
aph_555_qaa aph_670_qaa adg_412_qaa adg_443_qaa adg_490_qaa	Absorbtion due to phytoplankton at 555nm Absorbtion due to phytoplankton at 670nm  Absorbtion due to detritis and gelbstuff at 412nm Absorbtion due to detritis and gelbstuff at 443nm Absorbtion due to detritis and gelbstuff at 490nm

# **Bio-optical Products**

K_490 Diffuse Attenuation at 490nm using 490/555 K_532 Diffuse Attenuation at 532nm using 490/555  chl_oc2 Chlorophyll-a concentration using OC2 chl_oc4 Chlorophyll-a concentration using OC4 chl_stumpf Chlorophyll-a concentration using Stumpf chl_carder Chlorophyll-a concentration using Carder chl_trees Chlorophyll-a concentration using Trees chl_octsc chlorophyll-a concentration using the OCTS-C algorithm chl_nn chlorophyll-a concentration derived from pig_nn data chl_ndpi chlorophyll-a concentration derived from pig_ndpi data pig_oc2 pigment concentration derived from chl_oc2 pig_oc4 pigment concentration derived from chl_oc4 pig_octsc pigment concentration derived from chl_oc4 pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index  par photosynthetically active radiation depth water depth index  N_small_particles N_large_particles N_large_particles N_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity using Arnone's algorithm visibility diver visibility using 1.6/c (McBride)		
chl_oc2 Chlorophyll-a concentration using OC2 chl_oc4 Chlorophyll-a concentration using OC4 chl_stumpf Chlorophyll-a concentration using Stumpf chl_carder Chlorophyll-a concentration using Carder chl_trees Chlorophyll-a concentation using Trees chl_octsc chlorophyll-a concentration using the OCTS-C algorithm chl_nn chlorophyll-a concentration derived from pig_nn data chl_ndpi chlorophyll-a concentration derived from pig_ndpi data pig_oc2 pigment concentration derived from chl_oc2 pig_oc4 pigment concentration derived from chl_oc4 pig_octsc pigment concentration derived from chl_octsc pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index  Par photosynthetically active radiation depth water depth index  N_small_particles N_large_particles N_large_particles N_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity using Arnone's algorithm	K_490	Diffuse Attenuation at 490nm using 490/555
chl_oc4 Chlorophyll—a concentration using OC4 chl_stumpf Chlorophyll—a concentration using Stumpf chl_carder Chlorophyll—a concentration using Carder chl_trees Chlorophyll—a concentration using Trees chl_octsc chlorophyll—a concentration using the OCTS—C algorithm chl_nn chlorophyll—a concentration derived from pig_nn data chl_ndpi chlorophyll—a concentration derived from pig_ndpi data pig_oc2 pigment concentration derived from chl_oc2 pig_oc4 pigment concentration derived from chl_oc4 pig_octsc pigment concentration derived from chl_octsc pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index par photosynthetically active radiation depth water depth index  N_small_particles N_large_particles N_large_particles N_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	K_532	Diffuse Attenuation at 532nm using 490/555
chl_stumpf chl_carder chl_carder chl_trees chl_octsc chlorophyll-a concentration using Trees chl_nn chl_nn chlorophyll-a concentration derived from pig_nn data chl_ndpi pig_oc2 pig_oc4 pig_octsc pig_nn pig_nn pig_ndpi p	chl_oc2	Chlorophyll–a concentration using OC2
chl_carder chl_trees chl_octsc chlorophyll-a concentration using Trees chl_nn chlorophyll-a concentration using the OCTS-C algorithm chl_ndpi pig_oc2 pig_oc4 pig_octsc pig_nn pig_ndpi	chl_oc4	Chlorophyll–a concentration using OC4
chl_trees	chl_stumpf	Chlorophyll–a concentration using Stumpf
chl_octsc chlorophyll-a concentration using the OCTS-C algorithm chl_nn chlorophyll-a concentration derived from pig_nn data chlorophyll-a concentration derived from pig_ndpi data pig_oc2 pigment concentration derived from chl_oc2 pigment concentration derived from chl_oc4 pig_octsc pig_nn pigment concentration derived from chl_octsc pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index par photosynthetically active radiation depth water depth index  N_small_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity using Arnone's algorithm	chl_carder	Chlorophyll-a concentration using Carder
chl_nn chlorophyll-a concentration derived from pig_nn data chl_ndpi chlorophyll-a concentration derived from pig_ndpi data pig_oc2 pigment concentration derived from chl_oc2 pigment concentration derived from chl_oc4 pig_octsc pigment concentration derived from chl_octsc pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index par photosynthetically active radiation depth water depth index  N_small_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	chl_trees	Chlorophyll–a concentation using Trees
chl_ndpi chlorophyll-a concentration derived from pig_ndpi data pig_oc2 pig_oc4 pigment concentration derived from chl_oc2 pig_octsc pig_nn pigment concentration derived from chl_octsc pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index par photosynthetically active radiation depth water depth index  N_small_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	chl_octsc	chlorophyll-a concentration using the OCTS-C algorithm
pig_oc2 pigment concentration derived from chl_oc2 pig_oc4 pigment concentration derived from chl_oc4 pig_octsc pigment concentration derived from chl_octsc pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index par photosynthetically active radiation depth water depth index  N_small_particles N_large_particles N_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	chl_nn	chlorophyll-a concentration derived from pig_nn data
pig_oc4 pigment concentration derived from chl_oc4 pig_octsc pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index  par photosynthetically active radiation depth water depth index  N_small_particles N_large_particles N_particles N_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	chl_ndpi	chlorophyll-a concentration derived from pig_ndpi data
pig_octsc pigment concentration derived from chl_octsc pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index par photosynthetically active radiation depth water depth index  N_small_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	pig_oc2	pigment concentration derived from chl_oc2
pig_nn pigment concentration using neural network algorithm pig_ndpi pigment concentration using normalized diffence pigment index par photosynthetically active radiation depth water depth index  N_small_particles N_large_particles N_particles N_particles number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	pig_oc4	pigment concentration derived from chl_oc4
pig_ndpi pigment concentration using normalized diffence pigment index par photosynthetically active radiation depth water depth index  N_small_particles number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	pig_octsc	pigment concentration derived from chl_octsc
par photosynthetically active radiation depth water depth index  N_small_particles number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	pig_nn	pigment concentration using neural network algorithm
depth water depth index  N_small_particles number of small particles using Haltrin's algorithm  N_large_particles number of small particles using Haltrin's algorithm  N_particles number of small particles using Haltrin's algorithm  salinity salinity using Arnone's algorithm	pig_ndpi	pigment concentration using normalized diffence pigment index
N_small_particles number of small particles using Haltrin's algorithm N_large_particles number of small particles using Haltrin's algorithm N_particles number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	par	photosynthetically active radiation
N_large_particles number of small particles using Haltrin's algorithm N_particles number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	depth	water depth index
N_particles number of small particles using Haltrin's algorithm salinity salinity using Arnone's algorithm	N_small_particles	number of small particles using Haltrin's algorithm
salinity salinity using Arnone's algorithm	N_large_particles	number of small particles using Haltrin's algorithm
·	N_particles	number of small particles using Haltrin's algorithm
visibility diver visibility using 1.6/c (McBride)	salinity	salinity using Arnone's algorithm
	visibility	diver visibility using 1.6/c (McBride)

## **Land Products**

ndvi	normalized difference vegetation index
evi	enhanced vegetation index
smoke	smoke index

# **Quality control Products**

12_flags	Flags
flags_carder	Flags for Carder algorithm

## **Atmospheric Products**

aerindex	aerosol index
aer_model_min	minimum bounding aerosol model #
aer_model_max 1	maximum bounding aerosol model #
aer_model_ratio	model mixing ratio
aer_num_iter	number of aerosol iterations, NIR correction
	glint radiance normalized by solar irradiance
	retreived epsilon used for model selection
cloud_albedo d	cloud albedo at 865 nm
taua_412 a	aerosol optical depth at 412
taua_443 a	aerosol optical depth at 443
taua_490 a	aerosol optical depth at 490
taua_510 a	aerosol optical depth at 510
taua_555 a	aerosol optical depth at 555
taua_670 a	aerosol optical depth at 670
taua_765 a	aerosol optical depth at 765
taua_865 a	aerosol optical depth at 865
	aerosol angstrom coefficents (412,865)
	aerosol angstrom coefficents (443,865)
	aerosol angstrom coefficents (490,865)
	aerosol angstrom coefficents (510,865)
-	aerosol angstrom coefficents (555,865)
_	aerosol angstrom coefficents (670,865)
	aerosol angstrom coefficents (765,865)
angstrom_865	aerosol angstrom coefficents (865,865)
eps_412 1	ratio of 412
"F""	ratio of 443
eps_490 1	ratio of 490
1 -	ratio of 510
1 -	ratio of 555
*F * · ·	ratio of 670
"F"-" "	ratio of 765
eps_865 1	ratio of 865

## **Radiance Products**

## **Transmittance Products**

t_sol_412	Rayleigh-aerosol transmittance, sun to ground at 412
t_sol_443	Rayleigh-aerosol transmittance, sun to ground at 443
t_sol_490	Rayleigh-aerosol transmittance, sun to ground at 490
t_sol_510	Rayleigh-aerosol transmittance, sun to ground at 510
t_sol_555	Rayleigh-aerosol transmittance, sun to ground at 555
t_sol_670	Rayleigh-aerosol transmittance, sun to ground at 670
t_sol_765	Rayleigh-aerosol transmittance, sun to ground at 765
t_sol_865	Rayleigh-aerosol transmittance, sun to ground at 865
t_sen_412	Rayleigh-aerosol transmittance, ground to sensor at 412
t_sen_443	Rayleigh-aerosol transmittance, ground to sensor at 443
t_sen_490	Rayleigh-aerosol transmittance, ground to sensor at 490
t_sen_510	Rayleigh-aerosol transmittance, ground to sensor at 510
t_sen_555	Rayleigh-aerosol transmittance, ground to sensor at 555
t_sen_670	Rayleigh-aerosol transmittance, ground to sensor at 670
t_sen_765	Rayleigh-aerosol transmittance, ground to sensor at 765
t_sen_865	Rayleigh-aerosol transmittance, ground to sensor at 865
t_oz_sol_412	ozone transmittance, sun to ground at 412
t_oz_sol_443	ozone transmittance, sun to ground at 443
t_oz_sol_490	ozone transmittance,sun to ground at 490
t_oz_sol_510	ozone transmittance,sun to ground at 510
t_oz_sol_555	ozone transmittance,sun to ground at 555
t_oz_sol_670	ozone transmittance, sun to ground at 670
t_oz_sol_765	ozone transmittance, sun to ground at 765
t_oz_sol_865	ozone transmittance, sun to ground at 865
	-
t_oz_sen_412	ozone transmittance, ground to sensor at 412
t_oz_sen_443	ozone transmittance, ground to sensor at 443
t_oz_sen_490	ozone transmittance, ground to sensor at 490
t_oz_sen_510	ozone transmittance, ground to sensor at 510
t_oz_sen_555	ozone transmittance, ground to sensor at 555
t_oz_sen_670	ozone transmittance, ground to sensor at 670
t_oz_sen_765	ozone transmittance, ground to sensor at 765
t_oz_sen_865	ozone transmittance, ground to sensor at 865
t_o2_412	total oxygen transmittance at 412
t_o2_443	total oxygen transmittance at 443
t_o2_490	total oxygen transmittance at 490
t_o2_510	total oxygen transmittance at 510
t_o2_555	total oxygen transmittance at 555
t_o2_670	total oxygen transmittance at 670
t_o2_765	total oxygen transmittance at 765
t_o2_865	total oxygen transmittance at 865
_	

## **Reflectance Products**

rhos_412	surface reflectance at 412
rhos_443	surface reflectance at 443
rhos_490	surface reflectance at 490
rhos_510	surface reflectance at 510
rhos_555	surface reflectance at 555
rhos_670	surface reflectance at 670
rhos_765	surface reflectance at 765
rhos_865	surface reflectance at 865
rrs_412	Remote Sensing Reflectance at 412
rrs_443	Remote Sensing Reflectance at 443
rrs_490	Remote Sensing Reflectance at 490
rrs_510	Remote Sensing Reflectance at 510
rrs_555	Remote Sensing Reflectance at 555
rrs_670	Remote Sensing Reflectance at 670
rrs_765	Remote Sensing Reflectance at 765
rrs_865	Remote Sensing Reflectance at 865
foq_412	f/Q correction to nadir at 412
foq_443	f/Q correction to nadir at 443
foq_490	f/Q correction to nadir at 490
foq_510	f/Q correction to nadir at 510
foq_555	f/Q correction to nadir at 555
foq_670	f/Q correction to nadir at 670
foq_765	f/Q correction to nadir at 765
foq_865	f/Q correction to nadir at 865

## **Ancilliary Data Products**

windspeed	magnitude of wind at 10 meters
zwind	zonal wind speed at 10 meters
mwind	meridional wind speed at 10 meters
windangle	wind direction at 10 meters
water_vapor	precipital water concentration
humidity	relative humidity
pressure	barometric pressure
ozone	ozone concentration
fsol	solar distance correction (1-D, not an image)
solz	solar zenith angle
sola	solar azimuth angle
senz	satellite zenith angle
sena	satellite azimuth angle

## L3ProdFile

This variable can be set to a UNIX text file that contains a list of products for this region of interest. See an existing L3ProdFile for example of format. The default value is \$AUTO\_DATA/seawifs/seawifs\_def\_l2prod.dat"

## L4ProdFile

This variable can be set to a UNIX text file that contains a list of products for this region of interest. See an existing L4ProdFile for example of format. The default value is \$AUTO\_DATA/seawifs/seawifs\_def\_l4prod.dat"

#### L3ProdList

This is a space delimetered list of products to be written to the output data base. See the list above for possible product names.

For example, suppose we want to study the aerosol optical depth products to match up with sun photometer. Then we will add the following lines in our script (NOTE: these will be the *only* products in the output file – the default products will be ignored):

```
# Name all desired products
L3ProdList="taua_412 taua_443 taua_490 taua_510"
```

L3ProdList="\$L3ProdList taua 555 taua 670 taua 765 taua 865"

#### L4ProdList

This is a space delimetered list of products to be written to the output Level-4 data bases. See the list above for possible product names. The products listed here should also be listed as an Level-3 product.

## **Projection**

These variables control information about the projection for the Level-3 file and naming of the file based on projection.

## MapFile

Name of file containing image map file. Defaults to \$AutoData/maps.hdf.

## MapExt

This is a string that is appended to the Level–3 file which is written to the database. Usually it is a three character extension all uppercase.

#### MinPixels, MinLines

Used to set the minimum pixels/lines that must be extracted from the SeaWiFS file by swfExtract to continue processing. These are used to insure that enough of the input file covers the area of interest. By default these are not defined and, therefore, no check is performed.

## SwfAreaOpts

This allows the use of options to the **swfArea**(1) program to be added. However, this string sould not contain the -p, -l, or -M options.

#### **Data Base**

These variables control information about where the data base of Level-3 and Level-4 will reside and the structure of that data base.

Region This variable will be used to create the default data base directories. By default it set to \$Map-Name.

## SwfDataBase

This variable is used to indicate the location of the image data base for the generated product file. By default, it is set to:

\$DataBase/\$Level/\$Sensor/\$Version/\$Region/\$Year/\$Month.

#### where.

\$DataBase is defined in the aps.conf file and represents the top directory of the data base.

\$Level is set to the string "lvl3" by swfInit.

\$Sensor is set to the string "seawifs" by swfInit.

\$Version is set to "2.4" by swfInit.

\$Region is set to "\$MapName" by swfInit.

\$Year and \$Month are set by swfProcess based on the input file.

The user can override \$SwfDataBase since it is evaluated by the shell prior to use. For example, if the line:

```
SwfDataBase="\$DataBase/seawifs/\$Year"
```

is set in the areas script and we assume that \$DataBase is set to /data and that for a particular file \$Year has been set to 1999, then the product file will be moved to /data/seawifs/1999. Note that to use the variables, the user must "escape" the '\$' by inserting a "\".

#### SwfDAYDataBase

This variable is used to indicate the location of the Level–4 daily composites data base for the generated product file. By default, it is set to:

\$DataBase/\$CompLevel/\$Sensor/\$Version/\$Region/daily/\$Year/\$Month.

#### where,

\$DataBase is defined in the aps.conf file and represents the top directory of the data base.

\$CompLevel is set to the string "lvl4" by swfInit.

\$Sensor is set to the string "seawifs" by swfInit.

\$Version is set to "2.4" by swfInit.

\$Region is set to "\$MapName" by swfInit.

\$Year and \$Month are set by swfProcess based on the input file.

The user may override \$SwfDAYDataBase since it is evaluated by the shell prior to use.

#### SwfNDDataBase

This variable is used to indicate the location of the Level-4 weekly (8-day) composites data base for the generated product file. By default, it is set to:

\$DataBase/\$CompLevel/\$Sensor/\$Version/\$Region/weekly/\$Year.

#### where.

\$DataBase is defined in the aps.conf file and represents the top directory of the data base.

\$CompLevel is set to the string "lvl4" by swfInit.

\$Sensor is set to the string "seawifs" by swfInit.

\$Version is set to "2.4" by swfInit.

\$Region is set to "\$MapName" by swfInit.

\$Year is set by swfProcess based on the input file.

The user may override \$SwfNDDataBase since it is evaluated by the shell prior to use.

## SwfMODataBase

This variable is used to indicate the location of the Level–4 monthly composites data base for the generated product file. By default, it is set to:

\$DataBase/\$CompLevel/\$Sensor/\$Version/\$Region/monthly/\$Year.

#### where,

\$DataBase is defined in the aps.conf file and represents the top directory of the data base.

\$CompLevel is set to the string "lvl4" by swfInit.

\$Sensor is set to the string "seawifs" by swfInit.

\$Version is set to "2.4" by swfInit.

\$Region is set to "\$MapName" by swfInit.

\$Year is set by swfProcess based on the input file.

The user may override \$SwfMODataBase since it is evaluated by the shell prior to use.

#### SwfYRDataBase

This variable is used to indicate the location of the Level-4 yearly composites data base for the generated product file. By default, it is set to:

\$DataBase/\$CompLevel/\$Sensor/\$Version/\$Region/yearly.

#### where.

\$DataBase is defined in the aps.conf file and represents the top directory of the data base.

\$CompLevel is set to the string "lvl4" by swfInit.

\$Sensor is set to the string "seawifs" by swfInit.

\$Version is set to "2.4" by swfInit.

\$Region is set to "\$MapName" by swfInit.

The user may override \$SwfYRDataBase since it is evaluated by the shell prior to use.

### **CmpOpt**

This can be defined by the user to select the type of compression program to call for the output product file before it is moved to \$SwfDataBase. This option can be set to: "gzip", "compress", "bzip2" or "none". Only set CmpOpt to a compression type that is available on user's machine. Note: If the user has defined XNumChunks or that variable is defined by swfInit, then the HDF file will automatically be internally compressed and this variable should not be used.

## XNumChunks, YNumChunks

These are used to define the number of "chunks" in each direction which will be created by imgReformat program for the product files. By default, a large level-3 file will be rewritten in chunks (or "tiles") with each chunk being compressed. A chunk will be no larger than 640 by 640. So, if the map image is 2430 by 1810, then imgReformat will create a total of 12 chunks (4 across and 3 down). A 1500 by 1500 map image will be divided into 9 chunks (3 across and 3 down). A 600 by 300 map image will not be chunked.

## L3BrowseDir

This variable is used to indicate the location of for the browse images. By default, it is set to:

\$ImagBase/\$Level/\$Sensor/\$Version/\$Region/\$Year/\$Month.

ImagBase is set in the aps.conf file and represents the top directory of the browse data base. Level is set to the string "lvl3" by swfInit.

Sensor is set to the string "seawifs" by swfInit.

Version is set to "2.4" by swfInit.

Region is set to "\$MapName" by swfInit.

Year and Month are set by swfProcess based on the input file.

The user can override L3BrowseDir since it is evaluated by the shell prior to use. For example, if the line:

L3BrowseDir="\\$ImagBase/browse/\\$Year"

is set in the areas script and we assume that ImagBase is set to /data and that for a particular file Year has been set to 1999, then the browse image will be moved to /data/browse/1999.

## **Debugging**

The following variables can be set to help the user debug problems or retain files that are normally removed.

#### swfVerbose

This variable can be set to control the amount of debugging output for each swfScript function. The value should be set between 0 and 9, with a value of nine calling the Bourne Shell command set -x.

## KeepLogFile

This is the file that will accept all logging information. By default is it set to the input file (SeaW-iFS Level-1A file) plus .log.

## KeepLogFile

Define this variable to prevent swfProcess from removing the log file.

#### KeepParam

Define this variable to prevent swfProcess from removing any of the parameter files.

## KeepL2

Define this variable to prevent swfProcess from removing the Level-2 file.

## **SeaWiFS Compositing Options**

#### **SwfDAYCompOpts**

This allows the user to add specific options from the **imgMean**(1) program for the daily composites. The user should not use the following options, howver: -o, -v, -L, -c, -F, -H, -T, -m.

## **SwfNDCompOpts**

Like SwfDAYCompOpts except for weekly composites.

## SwfMOCompOpts

Like SwfDAYCompOpts except for monthly composites.

## SwfYRCompOpts

Like SwfDAYCompOpts except for yearly composites.

## SwfCompOpts

Like SwfDAYCompOpts except applied to all composites.

## CompTypes

A string containing a list of desired composites. May contain any of the following strings ("daily" "weekly" "monthly", "yearly", or "none"). By default it is defined as:

CompTypes="daily weekly monthly yearly". If you don't want a specific composite you can remove it. Note, however, that there is some dependencies.

NDay Used to define the number of days in a weekly composite. Currently set to 8.

#### **SeaWiFS Processing Parameters**

CalFile Name of calibration file to be used during Level-2 processing. Defaults to \$AUTO\_DATA/seaw-ifs/SEAWIFS\_SENSOR\_CAL.TBL-199909-time\_dep\_7jun99.

#### LandMask

Name of landmask file to be used during Level-2 processing. Defaults to \$AutoData/seaw-ifs/landmask.dat

#### WaterMask

Name of watermask file to be used during Level-2 processing. Defaults to \$AutoData/seaw-ifs/watermask.dat

## SwfAtmOpts

ms78siegel

This controls the atmospheric algorithm used.

ms78 Multi-scattering with 765/865 model selection ms68 Multi-scattering with 670/865 model selection

ms68siegel Multi-scattering with 670/865 model selection and Siegel NIR iteration ms78arnone0 Multi-scattering with 765/865 model selection and Arnone NIR iteration ms78arnone1 Multi-scattering with 765/865 model selection and Arnone NIR (+aph) iteration ms78arnone2 Multi-scattering with 765/865 model selection and Arnone NIR (+adg) iteration ms78arnone Multi-scattering with 765/865 model selection and Arnone NIR (+aph+adg) iteration ms78arnone0412it Multi-scattering with 765/865 model selection and Arnone NIR and Stumpf 412 iteration ms78arnone1412it Multi-scattering with 765/865 model selection and Arnone NIR (+aph) and Stumpf 412 iteration ms78arnone2412it Multi-scattering with 765/865 model selection and Arnone NIR (+adg) and Stumpf 412 iteration ms78arnone412it Multi-scattering with 765/865 model selection and Arnone NIR (+aph+adg) and Stumpf 412 it

Multi-scattering with 765/865 model selection and Siegel NIR iteration

ms78stumpf Multi-scattering with 765/865 model selection and STUMPF NIR (+aph+adg)

ms78stumpf412it Multi-scattering with 765/865 model selection and STUMPF NIR (+aph+adg) and STUMPF 4

ms78mumm Multi-scattering with 765/865 model selection and MUMM NIR calculation

#### SwfParamFile

Name of file containing additional options to the MS112 program. These should *not* contain the following options: par=, ifile=, ofile1=, l2prod1=, ofmt=, calfile= (use CalFile instead), land= (use LandMask instead), water= (use WaterMask instead), met1=, met2=, met3= (use SwfMetDir, SwfMetFile instead), ozone1=, ozone2=, ozone3= (use SwfOzoneDir, SwfOzoneFile instead). All others should present no problems. The user's options located in the file pointed to by SwfParam-File are appended the to parameter file automatically generated by swfScripts. See **MS112**(1) for other possible options.

## SwfOzoneDir, SwfOzoneFile

Normally, these are undefined and will cause the climatology ozone file located in the data/seawifs directory to be used.

To use the NRT ozone data, the user must download it from the Goddard DAAC. The variable SwfOzoneDir points to the location of the NRT ozone file(s). If SwfOzoneFile is not set, then swfProcess will use the input file's date to build the appropriate file name. If this file had been compressed using gzip or compress, it is uncompressed. If SwfOzoneFile is set, it must

be an uncompressed file -- swfProcess sends it straight to l2gen, which will die if the file is incorrect.

If SwfOzoneDir is undefined, or the file \$SwfOzoneDir/\$SwfOzoneFile is not a regular file, then climatology file will be used.

#### SwfMetDir, SwfMetFile

Like SwfOzoneDir and SwfOzoneFile defined above but for the MET data.

## **Browse Image Variables**

#### noBrowse

This keyword will force no browse images to be created. It must be set to the string "no", as in noBrowe="no".

## L3BrowseFile

This keyword selects the input ascii file for the default Level-3 browse image files. It defaults to \$AUTO DATA/seawifs/seawifs def l2browse.dat.

### L4BrowseFile

This keyword selects the input ascii file for the default Level-4 browse image files. It defaults to \$AUTO\_DATA/seawifs/seawifs\_def\_l4browse.dat.

## L3BrowseList

This is a list of whitespace delimetered Level-3 products which are converted to browse images. The products in this list *must* also be present in the L3ProdList variable. By default, the browse images listed in L3BrowseFile are created.

#### L4BrowseList

This is a list of whitespace delimetered Level-3 products which are converted to browse images. The products in this list *must* also be present in the L3ProdList variable. By default, the browse images listed in L3BrowseFile are created.

#### **BrowseOpts**

It defines the user's options for all browse image. For example, the user may remove the grids by adding the line:

```
BrowseOpts="-q"
```

to the scripts.

## \${prod}\_BrowseOpts

This defines the user's options for a particular product. For example, to produce an chlorophyll—a browse image that is 300 pixels by 400 lines and has a data range from 0.01 to 10.0 using a log10 scale, add the line:

```
chl_oc4_BrowseOpts="-f log10 -r 0.01,10.0 -R 20,199 -s 300,400"
```

in the areas script. See **imgBrowse**(1) for more information.

Note: For the other products (those list in \$L3ProdList above but not here), the user must

provide the corresponding variables as there are no defaults.

## **Program Variables**

These variables define the programs used by swfScripts. The user can overide these to test a new version of a program. They are defined in swfInit.

## ApsInfo

Set to the name of the satellite specific program used to obtain information from input Level-1 file. Defaults to \$AutoBin/swfInfo.

#### SwfArea

Set to the name of the program used to determine if a SeaWiFS file covers a map. Defaults to  $\Delta = \pi \sin \beta$ .

#### SwfL1L2

Set to the name of the program used to do the atmospheric correction and generate the remote sensing reflectance products. Defaults to \$AutoBin/MS112.

#### SwfInfo

Set to the name of the program used to obtain information from SeaWiFS file. Defaults to \$AutoBin/swfInfo.

## **CONFORMANCE**

These script functions attempt to conform to the IEEE 1003.2 POSIX Shell Standard. They were, however, developed and tested using the Bourne Shell and Korn Shells under IRIX 5.3 and IRIX 6.5 respectively.

## **EXAMPLES**

These script functions attempt to conform to the IEEE 1003.2 POSIX Shell Standard. They were, however, developed and tested using the Bourne Shell and Korn Shells under IRIX 5.3 and IRIX 6.5 respectively.

## **SEE ALSO**

 $apsScripts(1) \ \ daylight(1), \ \ filefmt(1), \ \ hdf(1), \ \ maps(1), \ \ imgMap(1), \ \ imgReformat(1), \ \ imgBrowse(1), \\ MSl12(1), swfArea(1), swfInfo(1), \\$ 

## **NAME**

swfSeadas - create bio-optical images from remote sensing reflectance

## **SYNOPSIS**

swfSeadas [options] inFile ouFile

## **DESCRIPTION**

The swfSeadas program will create bio-optical products of chlorophyll-a concentration and diffuse attenuation. By default, it creates the chlorophyll-a concentration using the SeaBAM oc2 algorithm, the diffuse attenuation at 490 nm using the SeaDAS 443/555 algorithm, and the diffuse attenuation at 532 nm using Mueller's 490/555 algorithm.

## **OPTIONS**

--version

Print out version and exit.

## **NAME**

swfStumpf - correct rrs spectrum

## **SYNOPSIS**

swfStumpf [options] inFile ouFile

## **DESCRIPTION**

The swfStumpf program will correct the Rrs spectrum using the rrs@412. It will also output Rick Stumpf's Southeast/Gulf of Mexico Case 2 chlorophyll-a product.

## **OPTIONS**

- -c Do not output Stumpf's chlorophyll-a product
- -C Do not correct the remote sensing reflectance.
- -d Output adg412 product
- -p Output aph443 product
- --version

Print out version and exit.

## **EXAMPLES**

To correct the rrs spectrum in file1.hdf and write the results to file2.hdf, but do not output the chlorophyll-a product:

```
$ swfStumpf -c file1.hdf file2.hdf
```

To use the rrs in file1.hdf and plact the chlorophyll-a concentration product in the same file.

```
$ swfStumpf -C file1.hdf file2.hdf
```

## **SEE ALSO**

**MSI12**(1)

## **NAME**

swfVisibility - creates diver visibility image from beam attenuation

## **SYNOPSIS**

swfVisibility [options] inFile [ouFile]

## **DESCRIPTION**

The swfVisibility program will generate a diver visibility image using an algorithm from McBride. The input file must be an HDF file with "c\_555\_Carder" which represents the beam attenuation at 555 nm. (We have found that Carder's beam attenuation product works better than the Arnone beam attenuation product). The output product will be called "visibility".

The McBride algorithm used here is a simple ratio algorithm.

## **OPTIONS**

-v Verbose

--version

Print out version and exit.

## **REFERENCES**

The McBride algorithm reference is unknown.

## **EXAMPLES**

The following example appends the visibility product to the input file.

```
$ swfVisibility rrs.hdf
```

## **SEE ALSO**

MSl12(1), swfCarder(1)